Enabling Replication

2025/04/05 15:45

To enable TapeTrack High Availability Replication:

Steps On Remote Server

Install the TapeTrack Framework Server software on your remote machine.

Stop the service on the remote machine.

Delete all database files on the remote machine (all files in the var/db directory EXCEPT the DB_CONFIG file).



Do Not delete the DB_CONFIG file.

Name Name	Date modified	Ту
TMSS10.dictionary-data	6/18/2018 10:06 AM	DI
TMSS10.dr-strategy	5/21/2018 9:56 AM	D
TMSS10.dr-strategy-item	5/21/2018 9:56 AM	DI
db.rep.egen	4/11/2018 9:36 AM	EC
TMSS10.emailspool	6/18/2018 10:06 AM	E
TMSS10.favorite DELE	5/3/2018 9:14 AM	FA
DB_CONFIG	6/14/2013 9:45 AM	Fi
TMSS10Server	1/31/2018 10:49 AM	Fi
TMSS10.file	3/9/2018 12:18 PM	FI
TMSS10.file-data	3/9/2018 12:18 PM	FI
TMSS10.file-generation	3/9/2018 12:18 PM	FI
db.rep.gen	4/11/2018 9:36 AM	G

Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 0** to make the machine a Replicant.

```
DB CONFIG - Notepad
                                                                        File Edit Format View Help
set verbose DB VERB WAITSFOR
#
#rep set priority 1
#repmgr site replicant-1.tapetrack.com 5010
#repmgr site master.tapetrack.com 5010 db local site on db group crea
#
# Optional settings
#
#rep set config DB REP CONF BULK on
#rep set config DB REP CONF AUTOINIT off
#
#
#rep set priority 0
#repmgr site replicant-1.tapetrack.com 5010 db local site on
#repmgr site master.tapetrack.com 5010 db bootstrap helper on
#rep set config DB REP CONF BULK on
```

Edit the Replicant Server and Master Server host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com** with the IP address of **your** Replicant Server (RRR.RRR.RRR.RRR used as Replicant IP example).
- Replace **master.tapetrack.com** with the IP address of **your** Master Server (MMM.MMM.MMM.MMM used as Master IP example).



Ensure you use the IP4 address for the Master and Replicant Server as using the domain name can cause issues with the IP6 address replacing the IP4 address, stopping the Master and Replicant communication.

```
"DB_CONFIG-Notepad
File Edit Format View Help
set_verbose DB_VERB_WAITSFOR
#
#repmgr_site replicant-1.tapetrack.com 5010
#repmgr_site master.tapetrack.com 5010 db_local_site on db_group_crea
#
# Optional settings
#
#rep_set_config DB_REP_CONF_BULK on
#rep_set_config DB_REP_CONF_AUTOINIT off
#
#
rep_set_priority 0
repmgr_site RRR.RRR.RRR.S010 db_local_site on
repmgr_site MMM.MMM.MMM_5010 db_bootstrap_helper on
rep_set_config DB_REP_CONF_BULK on
```



Ensure that the replication TCP/IP ports specified in the DB_CONFIG file are open for inbound connections.

Start the TapeTrack service on the remote machine.

Steps On Master Server

Stop the TapeTrack service on the master TapeTrack server.



Do Not delete any files on the master server

Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 1** to make the machine a master server.

```
DB CONFIG - Notepad
File Edit Format View Help
set verbose DB VERB WAITSFOR
#rep set priority 1
#repmgr site replicant-1.tapetrack.com 5010
#repmgr site master.tapetrack.com 5010 db local site on db group crea
#
# Optional settings
#
#rep set config DB REP CONF BULK on
#rep set config DB REP CONF AUTOINIT off
#
#
#rep set priority 0
#repmgr site replicant-1.tapetrack.com 5010 db local site on
#repmgr site master.tapetrack.com 5010 db bootstrap helper on
#rep set config DB REP CONF BULK on
```

Edit the DB_CONFIG file to define the local and remote server. Edit the replication local (master server) and remote (replicant server) host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com** with the domain name (or IP address) of **your** Replicant Server.
- Replace master.tapetrack.com with the domain name (or IP address) of your Master Server.

```
*DB_CONFIG - Notepad
File Edit Format View Help
set verbose DB VERB WAITSFOR
#
rep set priority 1
repmgr site RRR.RRR.RRR. 5010
repmgr site MMM.MMM.MMM.5010 db local site on db group creator
#
# Optional settings
#
#rep set config DB REP CONF BULK on
#rep set config DB REP CONF AUTOINIT off
#
#
#rep set priority 0
#repmgr site replicant-1.tapetrack.com 5010 db local site on
#repmgr site master.tapetrack.com 5010 db bootstrap helper on
#rep set config DB REP CONF BULK on
```

Ensure that the replication TCP/IP ports are open for inbound/outbound connections.

Start the master TapeTrack Server.

Confirming Functionality Of Primary And Replicant Servers

Open \$DB_Msg.txt file (in the var/db directory) on both the primary and replicant server to ensure that replication is functional.



Ensure that all firewall ports are open to allow the replication traffic to pass between the replicants.



The replication communications are not encrypted so if replication is enabled you should ensure that all machines that are replicated are in a trusted network or connected via a secure VPN connection.

Server replication troubleshooting

See Also

Restoring replicant server to master server status

From: https://rtfm.tapetrack.com/ - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/server/replication?rev=1578443328



Last update: 2025/01/21 22:07