2025/04/05 11:27 1/5 Enabling Replication

Enabling Replication

To enable TapeTrack High Availability Replication:

Steps On Remote Server


Install the TapeTrack Framework Server software on your remote machine.

Stop the service on the remote machine.

Delete all database files on the remote machine (all files in the var/db directory except the DB CONFIG file).



Do Not delete the DB CONFIG file.



Edit the DB_CONFIG file and remove the comments (#'s) from the line **rep-set-priority 0** to make the machine a Replicant.

```
DB CONFIG - Notepad
File Edit Format View Help
set verbose DB VERB WAITSFOR
#rep set priority 1
#repmgr site replicant-1.tapetrack.com 5010
#repmgr site master.tapetrack.com 5010 db local site on db group crea
# Optional settings
#
#rep set config DB REP CONF BULK on
#rep set config DB REP CONF AUTOINIT off
#
#
#rep set priority 0
#repmgr site replicant-1.tapetrack.com 5010 db local site on
#repmgr site master.tapetrack.com 5010 db bootstrap helper on
#rep set config DB REP CONF BULK on
```

Edit the replication local (replicant server) and remote (master server) host names in the DB_CONFIG file.

- Replace replicant-1.tapetrack.com 5010 with the domain name (or IP address) of your replicant server.
- Replace master.tapetrack.com 5010 with the domain name (or IP address) of your master server.

```
*DB_CONFIG - Notepad
File Edit Format View Help
set verbose DB VERB WAITSFOR
#rep set priority 1
#repmgr site replicant-1.tapetrack.com 5010
#repmgr_site master.tapetrack.com 5010 db_local_site on db_group_crea
# Optional settings
#
#rep set config DB REP CONF BULK on
#rep set config DB REP CONF AUTOINIT off
#
#
rep set priority 0
repmgr site RRR.RRR.RRR 5010 db local site on
repmgr site MMM.MMM.MMM 5010 db bootstrap helper on
rep set config DB REP CONF BULK on
```

https://rtfm.tapetrack.com/ Printed on 2025/04/05 11:27

2025/04/05 11:27 3/5 Enabling Replication



Ensure that the replication TCP/IP ports specified in the DB_CONFIG file are open for inbound connections.

Start the TapeTrack service on the remote machine.

Steps On Master Server

Stop the TapeTrack service on the master TapeTrack server.



Do Not delete any files on the master server

Edit the DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 1** to make the machine a master server.

```
| DB_CONFIG-Notepad | File Edit Format View Help | set_verbose DB_VERB_WAITSFOR | # | #rep_set_priority 1 | #repmgr_site replicant-1.tapetrack.com 5010 | #repmgr_site master.tapetrack.com 5010 | db_local_site on db_group_crea | # | Optional settings | # | #rep_set_config DB_REP_CONF_BULK on | #rep_set_config DB_REP_CONF_AUTOINIT off | # | # | #rep_set_priority 0 | #repmgr_site replicant-1.tapetrack.com 5010 | db_local_site on | #repmgr_site master.tapetrack.com 5010 | db_bootstrap_helper on | #rep_set_config DB_REP_CONF_BULK on | #rep_set_config DB_REP_CONF_
```

Edit the DB_CONFIG file to define the local and remote server. Edit the replication local (master server) and remote (replicant server) host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com 5010** with the domain name (or IP address) of **your** replicant server.
- Replace master.tapetrack.com 5010 with the domain name (or IP address) of your master server.

Last update: 2025/01/21 22:07

```
*DB_CONFIG - Notepad
File Edit Format View Help
set verbose DB VERB WAITSFOR
rep set priority 1
repmgr site RRR.RRR.RRR.RRR 5010
repmgr site MMM.MMM.MMM 5010 db local site on db group creator
#
# Optional settings
#
#rep set config DB REP CONF BULK on
#rep set config DB REP CONF AUTOINIT off
#
#
#rep set priority 0
#repmgr site replicant-1.tapetrack.com 5010 db local site on
#repmgr site master.tapetrack.com 5010 db bootstrap helper on
#rep set config DB REP CONF BULK on
```



Ensure that the replication TCP/IP ports are open for inbound/outbound connections.

Start the master TapeTrack server.

Confirming Functionality of Primary And replicant Servers

Open \$DB_Msg.txt file (in the var/db directory) on both the primary and replicant server to ensure that replication is functional.



Ensure that all firewall ports are open to allow the replication traffic to pass between the replicants.



The replication communications are not encrypted so if replication is enabled you should ensure that all machines that are replicated are in a trusted network or connected via a secure VPN connection.

From:

https://rtfm.tapetrack.com/ - TapeTrack Documentation

Permanent link:

https://rtfm.tapetrack.com/server/replication?rev=1529293251

Last update: 2025/01/21 22:07

