

Enabling Replication

The following information illustrates the steps required to enable a High Availability Replicant Server.

It is assumed that you already have a functional installation of TapeTrack Server running.


All steps must be performed in the order presented to create a successful connection between the Master and Replicant Server.

IP addresses included in the instructions are for demonstration only, these must be replaced with your correct values.

Steps On Remote Server

Install the TapeTrack Framework Server software on your Replicant machine.

Stop the service on the Replicant machine.



Navigate Windows File Explorer to the TapeTrack Framework Server installation directory (TapeTrack\TapeTrack Framework Server) to the var\db folder.

Delete all database files on the Replicant machine (all files in the TapeTrack\TapeTrack Framework Server\var\db directory) **EXCEPT** the [DB_CONFIG](#) file).

File Home Share View			
TapeTrack > TapeTrack Framework Server > var > db			
Search db			
Name	Date modified	Type	Size
\$DB_Err.txt	3/11/2021 9:37 AM	Text Document	
\$DB_Msg.txt	3/11/2021 9:37 AM	Text Document	
DB_CONFIG	3/10/2021 12:38 PM	File	
TMSS10.attribute-history	3/8/2021 3:11 PM	ATTRIBUTE-HISTO...	
TMSS10.attribute-history.dump	3/8/2021 3:11 PM	DUMP File	
TMSS10.attribute-history.save	3/8/2021 2:31 PM	SAVE File	
TMSS10.attributes	3/8/2021 3:10 PM	ATTRIBUTES File	
TMSS10.attributes.dump	3/8/2021 3:10 PM	DUMP File	
TMSS10.attributes.save	3/8/2021 2:31 PM	SAVE File	
TMSS10.attributetype	3/8/2021 3:10 PM	ATTRIBUTETYPE File	
TMSS10.attributetype.dump	3/8/2021 3:10 PM	DUMP File	
TMSS10.attributetype.save	3/8/2021 2:31 PM	SAVE File	
TMSS10.barcode	3/8/2021 3:03 PM	BARCODE File	
TMSS10.barcode.dump	3/8/2021 3:02 PM	DUMP File	
TMSS10.barcode.save	3/8/2021 2:31 PM	SAVE File	
TMSS10.catalog	3/8/2021 3:15 PM	CATALOG File	
TMSS10.catalog.dump	3/8/2021 3:14 PM	DUMP File	
TMSS10.catalog.save	3/8/2021 2:31 PM	SAVE File	
TMSS10.catalog-extent	3/8/2021 3:16 PM	CATALOG-EXTENT...	
TMSS10.catalog-extent.dump	3/8/2021 3:16 PM	DUMP File	
TMSS10.catalog-extent.save	3/8/2021 2:31 PM	SAVE File	
TMSS10.catalog-extent-time	3/11/2021 9:37 AM	CATALOG-EXTENT...	
TMSS10.catalog-extent-time.dump	3/8/2021 3:16 PM	DUMP File	
TMSS10.catalog-extent-time.save	3/8/2021 2:36 PM	SAVE File	
TMSS10.catalog-file	3/8/2021 3:17 PM	CATALOG-FILE File	
TMSS10.catalog-file.dump	3/8/2021 3:17 PM	DUMP File	

Open the DB_CONFIG file in Notepad, or equivalent text editor.


Edit the TapeTrack\TapeTrack Framework Server\DB_CONFIG file to remove the comments (#'s) starting from the line **rep-set-priority 0** to make the machine a Replicant.

Edit the Replicant Server and Master Server host names in the DB_CONFIG file.

- Replace **replicant-1.tapetrack.com** with the IP address of **your** Replicant Server (your_replicant_IP_address used as Replicant IP example).
- Replace **master.tapetrack.com** with the IP address of **your** Master Server (your_master_IP_address used as Master IP example).



Ensure you use the IP4 address for the Master and Replicant Server as using the domain name can cause issues with the IP6 address replacing the IP4 address, stopping the Master and Replicant communication.



```
DB_CONFIG - Notepad
File Edit Format View Help
set_flags DB_LOG_AUTOREMOVE
#
# Set the log directory to an alternate directory
#
set_lg_dir ..\dblogs
#
#
# Set Verbose Output
#
set_verbose DB_VERB_DEADLOCK
set_verbose DB_VERB_RECOVERY
set_verbose DB_VERB_REPLICATION
set_verbose DB_VERB_WAITSFOR
#
#rep_set_priority 1
#repmgr_site replicant-1.tapetrack.com 5010
#repmgr_site master.tapetrack.com 5010 db_local_site on db_group_creator on
#
# Optional settings
#
#rep_set_config DB REP_CONF_BULK on
#rep_set_config DB REP_CONF_AUTOINIT off
#
#
#rep_set_priority 0
#repmgr_site replicant-1.tapetrack.com 5010 db_local_site on
#repmgr_site master.tapetrack.com 5010 db_bootstrap_helper on
#rep_set_config DB REP_CONF_BULK on
```



Ensure that the replication TCP/IP ports specified in the [DB_CONFIG](#) file are open for inbound connections.

Steps On Master Server

Stop the TapeTrack service on the master TapeTrack server.




Do Not delete any files on the master server

Edit the TapeTrack\TapeTrack Framework Server\DB_CONFIG file and remove the comments (#'s) starting from the line **rep-set-priority 1** to make the machine a master server.

Edit the DB_CONFIG file to define the local and remote server. Edit the Replicant Server and Master

Server host names in the [DB_CONFIG](#) file.

- Replace **replicant-1.tapetrack.com** with the domain name (or IP address) of **your** Replicant Server (your_replicant_IP_address used as Replicant IP example).
- Replace **master.tapetrack.com** with the domain name (or IP address) of **your** Master Server (your_master_IP_address used as Master IP example).




The screenshot shows a Windows Notepad window with the title "*DB_CONFIG - Notepad". The window contains a configuration file with the following content:

```
set_flags DB_LOG_AUTOREMOVE
#
# Set the log directory to an alternate directory
# [
set_lg_dir ..\dblogs
#
#
# Set Verbose Output
#
set_verbose DB_VERB_DEADLOCK
set_verbose DB_VERB_RECOVERY
set_verbose DB_VERB_REPLICATION
set_verbose DB_VERB_WAITSFOR
#
#rep_set_priority 1
#repmgr_site replicant-1.tapetrack.com 5010
#repmgr_site master.tapetrack.com 5010 db_local_site on db_group_creator on
#
# Optional settings
#
#rep_set_config DB REP_CONF_BULK on
#rep_set_config DB REP_CONF_AUTOINIT off
#
#
#rep_set_priority 0
#repmgr_site replicant-1.tapetrack.com 5010 db_local_site on
#repmgr_site master.tapetrack.com 5010 db_bootstrap_helper on
#rep_set_config DB REP_CONF_BULK on
```

The Notepad window includes standard menu options (File, Edit, Format, View, Help) and status bar information (Ln 45, Col 2, 100%, Windows (CRLF), UTF-8).

Delete all, and only, the files starting with `_db.` and `db.rep..` This step is made easier if you sort the files in ascending order of file names to group them all together.

These files will be rebuilt when the server is restarted using the information of the new master and replicant details.



Ensure that the replication TCP/IP ports are open for inbound/outbound connections.

Start The Servers

[Start the TapeTrack service on the remote machine.](#)

The replicant server will prepare the database for connection to the master server and move into Start Pending mode while waiting for the master server to respond.

S TapeTrack Server Helper

Service	TMSS10SVC
Name	Start Pending
Status	4472
Binary	C:\Program Files\TapeTrack\TapeTrack Framework Server\TMSS10Server.exe
Options	
Home Directory	
Port	5000
Syslogd Server	
Enable Replication	True
Log File Name Type	0

Save Service Settings

Control Service

Update Software

Edit/View Files

Stop **Start** **Download and Update** **DB_CONFIG**

Promptly [Start the master TapeTrack Server](#).

The master server will now connect to the replicant server and load the database information across the connection. This may take time depending on the database size.

S TapeTrack Server Helper

Service	TMSS10SVC
Name	Stopped
Status	C:\Program Files\TapeTrack\TapeTrack Framework Server\TMSS10Server.exe
Binary	
Options	
Home Directory	
Port	5000
Syslogd Server	
Enable Replication	True
Log File Name Type	0

Save Service Settings

Control Service

Update Software

Edit/View Files

Start **Download and Update** **DB_CONFIG**

Confirming Functionality Of Primary And Replicant Servers

Open `$DB_Msg.txt` file (in the `var/db` directory) on both the primary and replicant server to ensure that replication is functional.



Ensure that all firewall ports are open to allow the replication traffic to pass between the replicants.

Master \$DB_Msg.txt file showing connection between master and replicant and the process of sending database information.

Replicant \$DB_Msg.txt file showing connection between master and replicant, validation of connection and receiving database information.


DB_Msg.txt - Notepad

File Edit Format View Help

```
2021-03-11 11:56:54 [850:968000][636/12292] REP_UNDEF: Read in gen 0
2021-03-11 11:56:54 [850:968000][636/12292] REP_UNDEF: Read in gen 1
2021-03-11 11:56:54 [850:968000][636/12292] REP_UNDEF: EID 0 is assigned for site 192.168.0.197:5010
2021-03-11 11:56:54 [850:968000][636/12292] REP_UNDEF: EID 1 is assigned for site 192.168.0.96:5010
2021-03-11 11:56:54 BDB2525 No log files found
2021-03-11 11:56:54 [850:984000][636/12292] REP_UNDEF: try join request to site site 192.168.0.96:5010
2021-03-11 11:56:54 [850:984000][636/12292] REP_UNDEF: connection established
2021-03-11 11:56:54 [851:15000][636/12292] REP_UNDEF: set membership for 192.168.0.197:5010 4 (was 0)
2021-03-11 11:56:54 [851:15000][636/12292] REP_UNDEF: set membership for 192.168.0.96:5010 4 (was 0)
2021-03-11 11:56:54 [851:15000][636/12292] REP_UNDEF: rep_start: Found old version log 19
2021-03-11 11:56:54 [851:15000][636/12292] CLIENT: var/db rep_send_message: msgv = 7 logv 19 gen = 0 ei
2021-03-11 11:56:54 [851:15000][636/15880] CLIENT: starting election thread
2021-03-11 11:56:54 [851:15000][636/12696] CLIENT: starting connector thread, eid 1
2021-03-11 11:56:54 [851:15000][636/11468] CLIENT: accepted a new connection
2021-03-11 11:56:54 [851:15000][636/12696] CLIENT: connecting to site 192.168.0.96:5010
2021-03-11 11:56:54 [851:15000][636/15880] CLIENT: var/db rep_send_message: msgv = 7 logv 19 gen = 0 ei
2021-03-11 11:56:54 [851:31000][636/12696] CLIENT: connection established
2021-03-11 11:56:54 [851:31000][636/11468] CLIENT: handshake from connecting site 192.168.0.96:5010 EID
2021-03-11 11:56:54 [851:31000][636/11468] CLIENT: handshake with no known master to wake election thre
2021-03-11 11:56:54 [851:31000][636/12696] CLIENT: connector thread is exiting
2021-03-11 11:56:56 [853:15000][636/15880] CLIENT: var/db rep_send_message: msgv = 7 logv 19 gen = 0 ei
2021-03-11 11:56:56 [853:15000][636/15896] CLIENT: var/db rep_process_message: msgv = 7 logv 19 gen = 1
2021-03-11 11:56:56 [853:15000][636/15896] CLIENT: var/db rep_send_message: msgv = 7 logv 19 gen = 0 ei
2021-03-11 11:56:56 [853:15000][636/16096] CLIENT: var/db rep_process_message: msgv = 7 logv 19 gen = 1
2021-03-11 11:56:56 [853:31000][636/16096] CLIENT: Election done; egen 1
2021-03-11 11:56:56 [853:31000][636/16096] CLIENT: Updating gen from 0 to 1 from master 1
2021-03-11 11:56:57 [853:31000][636/16096] CLIENT: egen: 2. rep version 7
2021-03-11 11:56:57 [853:31000][636/16096] CLIENT: No commit or ckp found. Truncate log.
2021-03-11 11:56:57 [853:31000][636/16096] CLIENT: 
```


Ln 40, Col 1 100% Windows (CRLF) UTF-8

Another way of testing the replication is correct and functioning is to [create a connection](#) to the replicant database through Tapemaster using the replicants IP address. Remember to use the replicants connection port (usually 5000) and not the replication data port (5010).



As this database is a replication of the master server, all user-ID's from the master are functional in the replicant server for login purposes.

When you connect to the replicant database you will receive a popup reminding you the server is Read Only. While you can view Customer, Media and Volume information, any attempted updates will be blocked by security protocols.



The replication communications are not encrypted so if replication is enabled you should ensure that all machines that are replicated are in a trusted network or connected via a secure VPN connection.

Server replication troubleshooting

See Also

[Restoring replicant server to master server status](#)

From:

<https://rtfm.tapetrack.com/> - TapeTrack Documentation



Permanent link:

<https://rtfm.tapetrack.com/server/replication?rev=1615428190>

Last update: **2025/01/21 22:07**