## **Executing Sync Using Netcat**

#### **Prerequisites**

- root or sudo privileges to install software and scripts.
- Knowledge of using vi or similar to create and enable scripts
- Netcat installed on your system, to check run the command ncat —version
- tcp access to the server TapeTrack database and Sync is installed on
- xinetd installed on the server TapeTrack database and Sync is installed on
- Knowledge on how to extract the Volume data from your backup server (eg TSM, NetBackup)

#### **Setting Up Sending Server**

Create a script (eg run-remote-sync.sh) on your sending server, with executable permissions.

Add the required code to extract the Volume data to be Sync'd with your TapeTrack (receiving) Server into a text or CSV file.

```
vmquery -W -a > report.txt
```

Add the call Netcat, including the IP address and Port of the receiving server, along with the input data file. In the example the IP is XXX.XXX.XXX and Port 4545, these need to be replaced with your actual IP and Port numbers.

You can also record the output from the Sync if required by redirecting the stdin stream to file (eg Sync-output.txt).

```
nc XXX.XXX.XXX 4545 < ./report.txt > Sync-output.txt
```

By placing both the vmquery code with the netcat execution code in the same script, you can schedule the script to run using cron or similar to execute the data extraction and call to the Sync process on the receiving server.

### **Setting Up Receiving Server**

Create an entry in the /etc/services file with the name of the service and port number and protocol. In this example we will use the service name receive-sync and the port 4545 to match the sending server details. These details can be modified to suit what name and port you require, as long as the sending and receiving ports match.

```
receive-sync 4545/tcp
```

Create the xinetd service file (receive-sync) in /etc/xinetd.d with the minimum code, with the optional inclusion of the only from = YYY.YYY.YYY.YYY.Only use the only from if your IP address (or

range) remain static.

```
service receive-sync
{
     disable
                       = no
     socket type
                       = stream
     protocol
                       = tcp
     port
                       = 4545
     wait
                       = no
     user
                       = root
     server_args = -S user:-password@localhost
only_from = YYY.YYY.YYY
                     = /etc/tapetrack/scripts/runSync.sh
     log on failure +=USERID
}
```

For other options see the Linux xinetd manual pages.

Restart the xinetd service to refresh the data.

```
systemctl restart xinetd
```

# Create Script To Execute When Port 4545 Request Is Received

Create a script at /etc/tapetrack/scripts/runSync.sh (or a location of your choice as long as the location matches the server address in the xinetd service file) and give it executable permissions.

Add the code to execute the Sync, including the full path to the ttidef file

```
#!/bin/bash
cd /etc/tapetrack/scripts/
/bin/TMSS10Sync -S user:-password@localhost -d netcat-sync.ttidef
exit
```

When the Sync program is executed by the sending server with a call to the port, the data file will be passed to the Sync program via the stdin stream.

Ensure the ttidef file is either in the same directory, or at the location stated in the script so the Sync program has access.

Examples of ttidef files:

- Backup Exec
- Commvault
- Data Protector
- NetBackup

https://rtfm.tapetrack.com/ Printed on 2025/12/01 11:09

- NetWorker
- Tivoli Storage Manager
- VEEAM

Output from the Sync process will be passed back to the sending server from the stderr stream to the stdin stream.

This can be altered to write the output to file on either computer by using the > and 2> redirection streams to text file if required.

technote, netcat, linux, sync, xinetd

From:

https://rtfm.tapetrack.com/ - TapeTrack Documentation

Permanent link:

https://rtfm.tapetrack.com/technote/netcat/linux\_sync?rev=1623809141

Last update: 2025/01/21 22:07

