2025/10/18 22:46 1/2 barcode-processing

=Overview=

When a barcode is scanned in TapeTrack it is sent to the Server component to be interpreted and split (or parsed) into its respective components.

```
=Barcode Syntax Rules=
```

A TapeTrack Barcode may be up to 20 characters in length and may contain a Customer-ID and Media-ID component and must contain at least a Volume-ID component.

```
=Parsing Logic=
```

The TapeTrack Server parses barcodes as follows:

#The unparsed barcode will be looked up in the Barcode Translation Table and if it is found the translated barcode will be substituted. #When a corresponding Barcode Interpretation Definition is found the barcode is split into Customer-ID, Media-ID and Volume-ID components. #If the Customer-ID and Media-ID components are not resolved then the Scanned Default Customer-ID and Scanned Default Media-ID values (if any) are used to set the Customer-ID and Media-ID. #If the Customer-ID and Media-ID components are not resolved then the User Profile Default Customer-ID and User Profile Default Media-ID values (if any) are used to set the Customer-ID and Media-ID. #If the Media-ID component remains unresloved and the Customer Properties has the No-Duplicate Volume-ID attribute set then the server will attempt to find the Media-ID for the unique Volume-ID if the Volume-ID exists. #Using the Customer-ID and Media-ID values the Media Properties are looked up. #If the Media Properties has the Remove Volume-ID Suffix value set and there is a matching suffix the suffix is removed. #If the Media Properties have the Modulo 43 option 'AND' there is no corresponding length exclusion all except the last digit of the component Volume-ID are processed through the Modulo 43 algorithm. #If the last digit of the Volume-ID does not match the calculated Modulo 43 value a barcode scanning error is returned. #If the last digit of the Volume-ID does match the calculated Modulo 43 value the barcode is returned with the Volume-ID component stripped of it's check digit.

=Additional Logic for Batch Programs=

Batch programs that parse barcodes will also check for the existence of the environment variable TMSS10BARCODECONFIG when the program starts.

This variable is used to define the path to a config file containing settings that influence how barcode is performed.

set TMSS10BARCODECONFIG=c:\tmss\etc\barcode.cfg
TMSS10ValidateBarcode

Example Batch Barcode Config File

```
 defaults = {
```

```
customer-id = "ACME";
media-id = "DL";
```

```
};
```

Last update: 2025/01/21 22:07

Programs that load the Barcode Config File

*TMSS10Sync *TMSS10Inventory *TMSS10ValidateBarcode

=See Also= *Modulo 43

Barcode Scanning

From:

https://rtfm.tapetrack.com/ - TapeTrack Documentation

Permanent link:

https://rtfm.tapetrack.com/barcode-processing?rev=1513955722





https://rtfm.tapetrack.com/ Printed on 2025/10/18 22:46