

Adjusting Slot Allocation

From time to time you may need to adjust a [Customers Slot](#) allocation based on increased or decreased [Volume](#) numbers.

Increasing Slot Allocation

Slotting allocation can be increased by either adding extra [zones](#) to the [Repository](#), or by increasing the [Slot](#) allocation within the currently assigned [Zones](#).

See [Maintaining A Zone](#) to add or increase Zone allocation.

Decreasing Slot Allocation

Removing Empty Slots

Decreasing [Slot](#) allocation for a [Customer](#) can be as simple as reducing the [Slots](#) allocated through the [Slot Edit Range Information](#) window, as long as the [Slots](#) being removed are sequential, unoccupied and from the end of the last Zone allocated.

Removing Slot allocation using this method must be from the last allocated Zone (if multiple Zones are assigned) from the high end of the Zone. The reason for this is if there are three Zones allocated, each with 100 Slots, TapeTrack interprets these as one continual Slot arrangement, 1 to 100 in Zone 1, 101 to 200 in Zone 2 and 201 to 300 in Zone 3. Reducing the Slot allocation from 300 to 250 by removing the last 50 Slots from Zone 3 keeps all lower Slotted tapes in the same number Slot. So a tape in Slot 248 would still in the same place (Zone 3, 48th slot). If you were to remove the 50 Slots in Zone 2, Zone 1 would still be Slots 1 to 100, Zone 2 would now be Slots 101 to 150 and Zone 3 would be 151 to 250, essentially putting Slot 248 now in the 98th Slot in Zone 3. This would put all Volumes in Zone 3 out 50 Slots in allocation vs physical location.

Removing Occupied Slots


If the [Slots](#) to be removed from allocation are currently occupied, completely or partially, the [Volumes](#) will need to be reslotted before this can be accomplished.




You must have enough empty [Slots](#) under the highwater mark to accommodate any [Volumes](#) currently slotted above the mark.

To remove these [Volumes](#) from the occupied [Slots](#):

- Right click the required [Repository](#) and select [Properties](#), or double click the [Repository](#) , and click on the [Options](#) tab.



- Set Highwater Offset to the number you wish to lower Slot allocation by. For example if you currently have 3000 Slots allocated and wish to reduce the allocation to 1000 Slots set the highwater offset to 2000 (3000 - 2000).



- Run the slotting program [TMSS10SlotAllocation](#) to re-slot any Volumes above the highwater mark.
- Decrease the slot allocation.

Edit Range Information

Zone Selection

Zone-ID: **2:2** Drawer 2 divider 2

Slot Start: 1 Level 01, Slot S01

Slot End: 2000 Level 100, Slot S20

Slot Total: 2000

Slots/Level: 20

Slot Ranges

Start Slot: Level/Slot:

End Slot: Level/Slot:

Total Slots: 1000

C-ID	M-ID	R-ID	Start	Slot	End
US03	LTO	OFFS	Level 01, Slot S01	1	Level 100, Slot S20

- Adjust the **Highwater Offset** back to zero to enable use of all allocated Slots.

Edit Repository: Offsite Vault

Identity Zones Slot Usage Options Usage History Movement History Certification

Allow Deletes	False
Allow Overlaps	False
De-assign from Container	False
Empty Container	False
Do not slot if Container	False
Do not slot	False
Require Tag	False
Require Tag Reset	False
No re-move	False
Disallow backward next move date changes	False
Reset Data Cluster	False
Confirm Container Contents	False
Move Container Contents	False
Late Threshold	0
Highwater Offset	0
Movement Mode	None
Next Repository	Library
Enable Slotting	True

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/adjusting_slot_allocation?rev=1638836854

Last update: **2025/01/21 22:07**

