Adding and Maintaining Barcode Administrations

Barcode Administration is used to create and maintain Barcode Rules.

Without Barcode Administration Rules set, barcodes cannot be read while using the Desktop Scanning Window.

Each Barcode Rule defines which characters in a given barcode correspond with the Customer-ID, Media-ID, and Volume-ID.

Barcode Administration

To add, view or modify a barcode rule open the barcode administration window by selecting Administration \rightarrow Barcode Administration.

M TapeTrack TapeMaster™ (GazillaByte LLC)								
File	Administration Favorites Tools	View Help						
	Active User List				r A			
	Client Licensing	7/39)			(
	Barcode Administration	(326/0) (2,319/38)	📓 Inventory <u>Q</u> [DR Strategies 👭 I	Data Clusters 🛛 🔟 Simp			
	Group/User Administration 😡		Volumes					
	Message List	069/0)						
	Server Options	/0)	ID	Current Location	Target Location			
	Server Statistics	8)	Enter text h 🍸	Enter text h 🝸	Enter text he 7			
	Stock Control	nter A (122/1)	00000016	Library	ġ			
	Zana Administration		000001L6	Library	ġ			
	Zone Administration]	000002L6	Library	ģ			
			000003L6	📓 Library	🐞 Offsite Vault 🦂			
			000004L6	📓 Library	🐞 Offsite Vault 👌			
لمحمد	and the second s	~~~~~	LANdapagesen	🌉_^\illeagay_~~~/				

Add a Barcode Rule

Barcode rules are used to identify Volumes and route them to a specific Customer or Media Type.

When a Barcode is scanned, TapeMaster will go through the Barcode Rule list from top to bottom to identify which rule must be followed to properly identify and direct that Volume.

To add a Barcode Rule right-click in the Barcode Administration window, hover the cursor over Insert and select After, Before, or At End or press the **Insert (INS)** key on the keyboard.

Barcode Administration						
▲ T Handlers Conversions						
Seq.	Description	Filter	Filter User	r	Customer-ID	Media-ID
000	Generic ?.?.*	×1 1cf 1c			1-1: Length(1)	3-3: Length(1)
001	Generic ?.??.*	After	Add	>	1-1: Length(1)	3-4: Length(2)
002	Generic ?.???.*	Before	Delete		1-1: Length(1)	3-5: Length(3) {
003	Generic ?.???.*	At End	Drint	、 、	1-1: Length(1)	3-6: Length(4)
004	Generic ??.?.*	ALENU		· · ·	1-2: Length(2)	4-4: Length(1)
005	Generic ??.??.*	??[]??[]*	Properti	ies	1-2: Length(2)	4-5: Length(2)
006	Generic ??.???.*	??[]???[]*	~14 *		1-2: Length(2)	4-6: Length(3) 👌
007	Generic ??.???.*	??[]????[]*	~15 *		1-2: Length(2)	4-7: Length(4)
IIII 008	Generic ???.?.*	???[]?[]*	~13 *		1-3: Length(3)	5-5: Length(1)
009	Generic ???.??.*	???[,-]??[,-]*	~14 *		1-3: Length(3)	5-6: Length(2)
010	Generic ???.??.*	???[]???[]*	~15 *		1-3: Length(3)	5-7: Length(3)
011	Generic ???.???.*	???[]????[]*	~16 *	~~~~	1-3: Length(3)	5-8: Length(4)

Double-click the rule ID for the barcode rule called * *New* * to set parameters.

I Barcode Administration							
▲ T Handlers Conversions							
Seq.	Description	Filter	Filter	User	Customer-ID	Media-ID	
000	** New **		~0	*			
001	Generic ?. ?. *	?[]?[]*	~11	*	1-1: Length(1)	3-3: Length(1)	
002	Generic ?.??.*	?[]??[]*	~12	*	1-1: Length(1)	3-4: Length(2)	
003	Generic ?.???.*	?[]???[]*	~13	*	1-1: Length(1)	3-5: Length(3)	
004	Generic ?.???.*	?[]????[]*	~14	*	1-1: Length(1)	3-6: Length(4)	
005	Generic ??.?.*	??[]?[]*	~12	*	1-2: Length(2)	4-4: Length(1)	
006	Generic ??.??.*	??[]??[]*	~13	*	1-2: Length(2)	4-5: Length(2)	
007	Generic ??.???.*	??[]???[]*	~14	*	1-2: Length(2)	4-6: Length(3) ;	
008	Generic ??.???.*	??[]????[]*	~15	*	1-2: Length(2)	4-7: Length(4)	
009	Generic ???.?.*	???[]?[]*	~13	*	1-3: Length(3)	5-5: Length(1)	
010	Generic ???.??.*	???[]??[]*	~14	*	1-3: Length(3)	5-6: Length(2)	
	Generic ???.??.*		~15	≉ ∽∿∽∽∽∽∽∽∼₁_	1-3: Length(3)	5-7: Length(3)	

Edit Barcode Window

The Edit Barcode window has four parameters:

- General Details
- Scope
- Editing
- Elements

Edit I	Baro	ode		\times	
En	nabled		True	^	
Ba	arcode Description		Generic ????.??.*		
	So	ope			
	Ba	rcode Pattern	????[]???[]*		
	Us	er Pattern	•		
	Ra	nge Start			
	Range End				
Ξ	Ec	liting			
	Ed	it Mask	0000000000000000000		
	Str	ip Characters			
Ξ	B	ements			
	Ξ	Customer-ID			
		Use substring	True		
		Substring First Character	1		
		Substring Last Character	4		
	Ξ	Media-ID			
		Use substring	True		
		Substring First Character	6		
		Substring Last Character	8		
	Ξ	Volume-ID			
		Use substring	True		
		Substring First Character	10		
		Substring Last Character	19		
				×	
			OK Carel		
			OK Cancel		

General Details

- Enabled: When set to "True," the Barcode Rule will be used to identify Volumes.
- **Barcode Description**: A brief description of the Barcode Rule.

Scope

- **Barcode Pattern**: The Barcode Pattern uses TapeTrack Filters to define what this type of Barcode looks like. For example, "????????![3-5]" would look for a 16 character barcode with periods in character positions 4 and 8, an L in character position 15 and any number between 3 and 5 in character position 16. If a scanned Barcode does not meet this pattern, the next Barcode Rule on the list will be referenced.
- **User Pattern**: Many enterprises include Customer-IDs in their User-IDs or have various other patterns to define a User. If this is the case, use TapeTrack Filters to enter patterns of Users that should have access to this rule. Using the asterisk (*) will make this Barcode Rule available to all Users.
- Range Start / Range End: Setting a range will set the scope of the Barcode Rule to a specific range of numbers or letters. For example, a Range of 000500L4 to 000750L4 will only apply this Barcode Rule to Volumes 000500L4 - 000750L4. Volumes below 000499L4 and above 000751L4 will require additional Barcode Rules.

Editing

The Editing subsection can be set to exclude specific characters from a barcode.

- **Strip characters**: Similarly, the Strip Characters tool will remove specified characters in the Barcode. For example, if the letter is "X" is used in the Strip Characters field, Barcode "BWIX.LTOX.000234L4" will have the "X" characters removed so that the Barcode is received in TapeMaster as "BWI.LTO.000234L4".

Elements

- **Use substrings**: When set to "true" for a Customer-ID, object:media|Media-ID]] or Volume-ID, fields will appear to set "Substring First Character" and "Substring Last Character". These fields are used to set the range of the barcode that corresponds with the specified object ID. For example, in Barcode "BWI.LTO.000234L4" the Volume-ID begins with character 9 and ends with character 16, so the Substring First Character would be 9 and the Substring Last Character would be 16.
- Literals: When "Use Substrings" is set to "false" for a Customer-ID, Media-ID or Volume-ID, a field will appear that allows for the definition of literals. A "literal," in this context, is a Customer-ID, Media-ID or Volume-ID that can be assumed when the above Scope is used.

From: https://rtfm.tapetrack.com/ - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/admin_barcode?rev=1508879158



Last update: 2025/01/21 22:07