

Automate Volume Movement Based On Container Movement

Volumes can be removed from the assigned container automatically when the container move is confirmed into a selected repository. This function can be useful in situations where returning volumes assigned to a container are always removed and placed in a library or racking, saving an operator from having to complete this procedure manually.

This function is set at a repository level and thus can be limited to movements to only one repository, or as many as required.

Example

Business ACME writes data to tape, packs the volumes into a barcoded container, seals it, and sends it to an offsite vault. The vault confirms arrival of the container and places it, still sealed, into their storage rack.

When the container is recalled the vault ships it back to ACME. On delivery the container is opened and the volumes are placed back in racking for scratch volumes to be re-used. The container, empty, is then placed back in storage until required again.


In this example the volumes being written to live in the Library (LIBR) repository, vaulting is the Offsite (OFFS) repository and the scratch volumes are stored in the Scratch (SCRA) repository. Volume rotation is from LIBR → OFFS → SCRA → LIBR

We set any container in a move status to OFFS to move any volumes contained within it and as the vault does not open the containers we also set OFFS to confirm any volumes when it is itself confirmed.

We set any container in a move status to SCRA repository to move any volumes contained within it and to automatically remove those volumes from the container on confirmation of delivery. The volumes are scanned in to the scratch racking individually, so are not automatically confirmed as they were at the vault.

Settings

Offsite (OFFS) repository



Type	Vault
Scratch Mode	No Change
Scratch Priority	0
Offsite	True
Primary	False
No Distribution	False
Internal	False
Sort Sequence	0
Force Simple Management	True
No Next Repository	False
Allow Deletes	False
Allow Overlaps	False
De-assign from Container	False
Empty Container	False
Do not slot if Container	False
Do not slot	False
Require Tag	False
Require Tag Reset	False
No re-move	False
Disallow backward next move date changes	False
Reset Data Cluster	False
Confirm Container Contents	True
Move Container Contents	True
Late Threshold	0
Highwater Offset	0
Movement Mode	None
Next Repository	Scratch

Scratch (SCRA) repository

Identity	Zones	Slot Usage	Options	Usage History	Movement History	Certification
Type	Scratch					
Scratch Mode	No Change					
Scratch Priority	0					
Offsite	False					
Primary	False					
No Distribution	False					
Internal	False					
Sort Sequence	0					
Force Simple Management	False					
No Next Repository	False					
Allow Deletes	False					
Allow Overlaps	False					
De-assign from Container	False					
Empty Container	True					
Do not slot if Container	False					
Do not slot	False					
Require Tag	False					
Require Tag Reset	False					
No re-move	False					
Disallow backward next move date changes	False					
Reset Data Cluster	False					
Confirm Container Contents	False					
Move Container Contents	True					
Late Threshold	0					
Highwater Offset	0					
Movement Mode	None					
Next Repository	Library					

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/remove_volume_container_auto?rev=1536280160

Last update: **2025/01/21 22:07**

