

Slotting

A Slot is a location in a [Zone](#) large enough for one [Volume](#). Slotting is a process of allocating a volume to a particular slot to allow documentation of the exact storage location of that volume.

Adding Slots to a Repository

To add Slots to a [Repository](#), create a [Zone](#) using the Zone Administration tool in the Administration Menu. Then, follow the steps to [Add a Zone](#) to a Repository.

Manually Add a Volume to a Slot

To manually add a Volume to a Slot, double-click a [Volume](#) in the Volume List or right-click a [Volume](#) in the Volume List and select **Properties**. This will launch the [Volume Properties Window](#).

Select the **Target Location** tab and enter a Slot number in either the Slot field in the Relative Location window or the Level field and Slot field in the Absolute Location window.

Edit Volume: 000022L5

Identity Target Location Current Location Scanned Location Notes History

Relative Location

Repository-ID OFFS Offsite Vault

Slot 5 Maximum=60

Absolute Location

Zone-ID Drawer 1 divider 1

Level 1

Slot 5

Update Statistics

Click Save and the [Volume](#) will be put into a Move to that slot, even if that [Volume](#) is moving to a Slot within its Current [Repository](#).

Press F5 in the inventory window to update the display to show new target slotting.

Automatic Slotting

Automatic Slotting in TapeTrack is done with a Command Line program called [TMSS10SlotAllocation](#) that is included in installs of [TapeTrack Framework Server](#) and [TapeTrack Server Utilities](#) in

conjunction with [Windows Task Scheduler](#).

[TMSS10SlotAllocation](#) must be run on the [TapeTrack Framework Server](#), but it can be launched remotely if necessary.

Sample Slotting Script

```
TMSS10SlotAllocation -S superuser:-password@tapetrack.domain.com >  
"%TMSS10REPORTS%\slotting_report.txt" 2>  
"%TMSS10REPORTS%\slotting_error.txt"
```

Preparing TapeMaster for Automatic Slotting

Before running [TMSS10SlotAllocation](#) , Repositories must be set so that Slotting is Enabled. This can be done under the [Options Tab](#) of the [Repository Properties Window](#).



Once **Slotting** is enabled, the slotting Assignment Options can be set.

- **Slotting Mode**

- **IntelliSlot:** The Slotting batch process will Slot **Volumes** in groups by Consignment or Slotting Order until the available group slots are filled. At this point, empty Slots will be filled on a First Available Status.
- **First Available:** **Volumes** will be put in the first available Slot in their Repository and will not be grouped.
- **Bypass:** When **Volumes** are automatically confirmed (see above), they will not be assigned Slots.

- **Ignore Home Slot:** If a Volume has been assigned a Home Slot in the Options Tab of the **Volume Properties Window**, this Repository will ignore it and Slot using the Slot assignment Options.
- **Do not reslot:** If set to true a Volume will not be reslotted in it's previous slot when it is moved back.
- **Retain moving slot:** If set to true the slot allocation is not made available for other volumes

until the volume moving out is confirmed at target location. False allows the slot to be allocated to another volume as soon as the occupying volume is placed in a move status.

- **Slotting Order:** There are three orders with which Volumes may be assigned Slots:
 - **Movement Time:** Volumes will be assigned Slots based on when they arrived at the selected Repository.
 - **From Location:** Volumes will be assigned Slots based on which Repository they were sent from.
 - **Volume-ID:** Volumes will be assigned Slots in the alphanumeric order based on their Volume-IDs.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/master/slotting?rev=1566186140>

Last update: **2025/01/21 22:07**

