

Slotting

A Slot is a location in a [Zone](#) large enough for one [Volume](#). Slotting is a process of allocating a [master:volumes|Volume]] to a particular slot to allow documentation of the exact storage location of that [master:volumes|Volume]].

Adding Slots to a Repository

To add Slots to a [Repository](#), create a [Zone](#) using the Zone Administration tool in the Administration Menu. Then, follow the steps to [Add a Zone](#) to a Repository.

Manually Add a Volume to a Slot

To manually add a [master:volumes|Volume]] to a Slot, double-click a [Volume](#) in the [master:volumes|Volume]] List or right-click a [Volume](#) in the Volume List and select **Properties**. This will launch the [Volume Properties Window](#).

Select the **Target Location** tab and enter a Slot number in either the Slot field in the Relative Location window or the Level field and Slot field in the Absolute Location window.

The screenshot shows the 'Edit Volume: 000022L5' window with the 'Target Location' tab selected. The 'Relative Location' section includes a 'Repository-ID' dropdown set to 'OFFS' (Offsite Vault) and a 'Slot' spinner set to 5, with a 'Maximum=60' label. The 'Absolute Location' section includes a 'Zone-ID' dropdown set to 'Drawer 1 divider 1', a 'Level' spinner set to 1, and a 'Slot' spinner set to 5. An 'Update Statistics' button is located at the bottom of the window.

Click Save and the [Volume](#) will be put into a Move to that slot, even if that [Volume](#) is moving to a Slot within its Current [Repository](#).

Press F5 in the inventory window to update the display to show new target slotting.

Automatic Slotting

Automatic Slotting in TapeTrack is done with a Command Line program called [TMSS10SlotAllocation](#) that is included in installs of [TapeTrack Framework Server](#) and [TapeTrack Server Utilities](#) in conjunction with [Windows Task Scheduler](#).

[TMSS10SlotAllocation](#) must be run on the [TapeTrack Framework Server](#), but it can be launched remotely if necessary.

Sample Slotting Script

```
TMSS10SlotAllocation -S user:-password@tapetrack.domain.com >
"%TMSS10REPORTS%\slotting_report.txt" 2>
"%TMSS10REPORTS%\slotting_error.txt"
```

Preparing TapeMaster for Automatic Slotting

Before running [TMSS10SlotAllocation](#), Repositories must be set so that Slotting is Enabled. This can be done under the [Options Tab](#) of the [Repository Properties Window](#).

Edit Repository: Offsite Vault

Identity Zones Slot Usage Options Usage History Movement History Certification

Allow Deletes	False
Allow Overlaps	False
De-assign from Container	False
Empty Container	False
Do not slot if Container	False
Do not slot	False
Require Tag	False
Require Tag Reset	False
No re-move	False
Disallow backward next move date changes	False
Reset Data Cluster	False
Confirm Container Contents	False
Move Container Contents	False
Late Threshold	0
Highwater Offset	0
Movement Mode	None
Next Repository	Library
Enable Slotting	True
Slot Assignment Options	
Slotting Mode	IntelliSlot
Ignore Home Slot	False
Do not reslot	False
Retain moving slot	False
Slotting Order	Movement Time
Capacity	
Coordinates	

Save Cancel Help

Once **Slotting** is enabled, the slotting Assignment Options can be set.

- **Slotting Mode**

- **IntelliSlot:** The Slotting batch process will Slot **Volumes** in groups by Consignment or Slotting Order until the available group slots are filled. At this point, empty Slots will be filled on a First Available Status.
- **First Available:** **Volumes** will be put in the first available Slot in their Repository and will not be grouped.
- **Bypass:** When **Volumes** are automatically confirmed (see above), they will not be assigned Slots.

- **Ignore Home Slot:** If a Volume has been assigned a Home Slot in the Options Tab of the [Volume Properties Window](#), this Repository will ignore it and Slot using the Slot assignment Options.
- **Do not reslot:** If set to true a **Volume** will not be reslotted in it's previous slot when it is moved back.
- **Retain moving slot:** If set to true the slot allocation is not made available for other **Volumes**

until the [master:volumes|Volumes]] moving out is confirmed at target location. False allows the slot to be allocated to another **Volume** as soon as the occupying **Volume** is placed in a move status.

- **Slotting Order:** There are three orders with which **Volumes** may be assigned Slots:
 - **Movement Time:** **Volumes** will be assigned Slots based on when they arrived at the selected Repository.
 - **From Location:** **Volumes** will be assigned Slots based on which Repository they were sent from.
 - **Volume-ID:** **Volumes** will be assigned Slots in the alphanumeric order based on their **Volume-ID's**.

[slot](#), [slotting](#)

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/master/slotting?rev=1567105602>

Last update: **2025/01/21 22:07**

