

# Barcode Interpretation Definition

A Barcode Interpretation Definition uses a string pattern to identify the Barcodes format and handle the Barcode accordingly.

The string pattern allows the dissection, translation or substitution of a Barcode to identify [Customer-ID](#), [Media-ID](#) and [Volume-ID](#).

To view, add, remove or alter current Barcode Interpretation Definitions, open the [Barcode Administration](#) window in TapeMaster.

The screenshot displays the TapeTrack TapeMaster™ (GazillaByte LLC) application window. The interface includes a menu bar (File, Administration, Favorites, Tools, View, Help) and a Customer Filter input field. On the left, a tree view shows the hierarchy: GazillaByte LLC - Products > US00 - United States > US01 - New York > US02 - Los Angeles > CONT - Containers > LTO - LTO Cartridges > US03 - North Carolina. The main area is titled 'Volumes' and shows a table for 'Los Angeles Data Center LTO Cartridge'. The table has columns for ID, Current Location, Target Location, Next Move, and Description. Below the table, it shows 'Total Items: 1,585'. At the bottom, there is a 'Repositories' section with icons for Gemtrac, Library, Transport, and Offsite Vault. The status bar at the bottom indicates 'Connection 127.0.0.1 uses AES 256 bit encryption'.

ID	Current Location	Target Location	Next Move	Description
000057L6	Offsite Vault		Permanent	
000058L6	Offsite Vault		Permanent	
000059L6	Library		Permanent	
000060L6	Offsite Vault		Permanent	
000061L6	Library		Permanent	
000062L6	Library		Permanent	
000063L6	Offsite Vault		Permanent	
000064L6	Offsite Vault		Permanent	
000065L6	Library		Permanent	
000066L6	Offsite Vault	Library	Permanent	
000067L6	Library		Permanent	
000068L6	Library		Permanent	
000069L6	Offsite Vault	Library	Permanent	
000070L6	Offsite Vault	Library	Permanent	
000071L6	Library		Permanent	
000072L6	Offsite Vault	Library	Permanent	
000073L6	Offsite Vault		Permanent	

## Barcode Administration

When TapeTrack is installed the Barcode Administration window comes with generic Barcode definitions pre-installed. These Barcode definitions will handle the majority of standard Barcode

formats. If you use a custom formatted Barcodes or deal with Customers that do you will need to add Barcode definitions to instruct TapeTrack how to read them.

Barcode definition are read by TapeTrack from the top of the list (position 000) sequentially to the last definition, stopping when a match is found. It is therefore important to make sure your list is structured in such a way that the correct Barcode definition is used to parse the Barcodes.

For example, if you had a current barcode definition which encompassed most of your Volume-ID's but had a handful of Volume-ID's that needed customised processing but still met the above pattern, you would need to place the customised definition before it as the first compatible definition will be used.

### Add New Barcode Definition

Right click on a current Barcode Definition in a position you want to add the new definition to. Select Add and then Before, After or End depending on where you want the new definition added to.

Barcode Administration

HandlersConversions

Seq.	Description	Filter	Filter...	User	Customer-ID	Media-ID	Volume-ID
000	Generic ?.?.*	?[-]?[-]*	~11	*	1-1: Length(1)	3-3: Length(1)	5-14: Leng
001	Generic ?.??.*	?[-]?[-]*	~12	*	1-1: Length(1)	3-4: Length(2)	6-15: Leng
002	Generic ?.???.*	?[-]?[-]*	~13	*	1-1: Length(1)	3-5: Length(3)	7-16: Leng
003	Generic ?.????.*	?[-]?[-]*	~14	*	1-1: Length(1)	3-6: Length(4)	8-17: Leng
004	Generic ???.*	??[-]?[-]*	~12	*	1-2: Length(2)	4-4: Length(1)	6-15: Leng
005	Generic ???.?.*	??[-]?[-]*	~13	*	1-2: Length(2)	4-5: Length(2)	7-16: Leng
006	Generic ???.??.*	??[-]?[-]*	~14	*	1-2: Length(2)	4-6: Length(3)	8-17: Leng
007	Generic ???.???.*	??[-]?[-]*	~15	*	1-2: Length(2)	4-7: Length(4)	9-18: Leng
008	Generic ????.*	???[-]?[-]*	~13	*	1-3: Length(3)	5-5: Length(1)	7-16: Leng
009	Generic ????.?.*	???[-]?[-]*	~14	*	1-3: Length(3)	5-6: Length(2)	8-17: Leng
010	Generic ????.??.*	???[-]?[-]*	~15	*	1-3: Length(3)	5-7: Length(3)	9-18: Leng
011	Generic ????.???.*	???[-]?[-]*	~16	*	1-3: Length(3)	5-8: Length(4)	10-19: Leng
012	Generic ????.??.*	????[-]?[-]*	~14	*	1-4: Length(4)	6-6: Length(1)	8-17: Leng
013	Generic ????.??.*	????[-]?[-]*	~15	*	1-4: Length(4)	6-7: Length(2)	9-18: Leng
014	Generic ????.???.*	????[-]?[-]*	~16	*	1-4: Length(4)	6-8: Length(3)	10-19: Leng
015	Generic ????.????.*	????[-]?[-]*	~17	*	1-4: Length(4)	6-9: Length(4)	11-20: Leng
016	Long Barcode Hash	??????????*	~12	*			#
017	Space Barcode Hash	*? ?*	~5	*			#
018	Generic *	*	~1	*			1-10: Leng

### Edit New Barcode Definition

Right click on the new barcode definition and select Properties, or double click, to open the Edit

Barcode window.

## Barcode Fields

- Enabled
  - True: Barcode Definition is active.
  - False: Barcode Definition is not active.
- Barcode Description: Description of Barcode Definition, usually identifying definition action.
- Scope
  - Barcode Pattern
  - User Pattern
  - Range Start
  - Range End
- Editing
  - Edit Mask
  - Strip Characters
- Elements: Fields displayed for the Elements depend on the value chosen for Use Substring
  - Customer-ID
    - Use Substring
      - False Does not use a substring (portion of the Barcode) for Customer-ID
        - Literal: Only visible when Use Substring set to False. Use a literal value for Customer-ID.
      - True: Uses a substring (portion of the Barcode) for Customer-ID
        - Substring First Character: Only visible when Use Substring set to True. Position of start of substring of Customer-ID.
        - Substring Last Character: Only visible when Use Substring set to True. Position of end of substring of Customer-ID.
  - Media-ID
    - Use Substring
      - False Does not use a substring (portion of the Barcode) for Media-ID
        - Literal: Only visible when Use Substring set to False. Use a literal value for Media-ID.
      - True: Uses a substring (portion of the Barcode) for Media-ID
        - Substring First Character: Only visible when Use Substring set to True. Position of start of substring of Media-ID.
        - Substring Last Character: Only visible when Use Substring set to True. Position of end of substring of Media-ID.
  - Volume-ID
    - Use Substring
      - False Does not use a substring (portion of the Barcode) for Volume-ID
        - Literal: Only visible when Use Substring set to False. Use a literal value for Volume-ID.
      - True: Uses a substring (portion of the Barcode) for Volume-ID
        - Substring First Character: Only visible when Use Substring set to True. Position of start of substring of Volume-ID.
        - Substring Last Character: Only visible when Use Substring set to True. Position of end of substring of Volume-ID.

Editing new Barcode Definition for long duplicate Barcodes,

- Matching filter ????????DUP-?? (eg. 004762L3DUP-01)
- Limited to User-ID's starting with US
- Drop characters UP-0 from Barcode using mask 00000000011110

Edit Barcode

Enabled

True

Barcode Description

\*\* New \*\*

Scope

Barcode Pattern

User Pattern

\*

Range Start

Range End

Editing

Edit Mask

00000000000000000000

Strip Characters

Elements

Customer-ID

Use substring

False

Literal

Media-ID

Use substring

False

Literal

Volume-ID

Use substring

True

Substring First Character

1

Substring Last Character

10

OK

Cancel

## Further Examples

For a range of Barcode definitions see [Barcode Definition Examples](#).

From:  
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
<https://rtfm.tapetrack.com/technote/barcode-interpretation-definition>

Last update: **2025/01/21 22:07**

<https://rtfm.tapetrack.com/>

Printed on 2026/02/03 19:50