

TMSS10MovePending

Puts [Volumes](#) with a **Move Pending Flag** into a Move Status to the [Volume's Current Repository](#)'s Next Repository, as set in the Options Tab of the Repository Properties Window. If the [Volume's](#) current Repository has no Next Repository, the **Move Pending Flag** will be added, but no move will be initiated.

Synopsis

```
TMSS10MovePending [-S server] [-T test mode] [-V volume filter] [-c config file] [-o override file]
```

Options

- -S The Logon String argument sets the [Server Logon Information](#)
- -T Test mode, default = false..
- -V [Volume Filter](#) which can be used to filter the traversal of [Customer](#), [Media](#), [Volume](#), [Repository](#) and [Flag](#) values.
- -c The config file argument specifies the path to the Batch Configuration File. The Batch Configuration File allows you to perform advanced traversal of [Customer](#), [Media](#) and [Volumes](#), perform advanced Barcode pre and post processing and route program output to syslogd.
- -o Overide file location.

If an argument value starts with the value **FI:**, the value for that attribute will be read from the file name specified immediately after it. For example, if a file named `ACME_volumes` has the content `ACME_*.*`, specifying `FI:/etc/ACME_volumes` will have the same effect as `-V ACME.*.*`. Using **FI:** to refer to a file for an attribute value works for all attributes.

If the pattern being matched starts with ***LIST:** then rather than matching the literal value, each record in the file specified as ***LIST:filename** will be tested. If one matches the match will succeed.

2021/06/16 02:14 · Scott Cunliffe
[include page](#)

Technical Support

The TapeTrack Software is commercially supported by a full time help desk staff.

If you are experiencing problems or want some advice on how to configure or use the product please see the [Accessing Technical Support](#) page.

Exit Statuses

1. **zero** Program has ended successfully.

2. **non-zero** Program has not ended successfully.

Files

stdout: Output Reports.

stderr: Diagnostic messages.

Example

Command Line Syntax

```
TMSS10MovePending -S user:-password@localhost -V "US01.LT0.*"
```

Output

See Also

[Command Line Utility Troubleshooting and Diagnosis](#)

Changelog

Cannot load rss feed.

[update doco](#)

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**



Permanent link:

<https://rtfm.tapetrack.com/cli/tmss10movepending>

Last update: **2025/07/04 04:48**