

TMSS10ZoneList

TMSS10ZoneList lists each [Zone](#) and the [Volumes](#) assigned to them.

Synopsis

```
TMSS10ZoneList [-S logon string] [-V volume filter] [-f report format]
```

Options

- -S The Logon string argument sets the [Server Logon Information](#)
- -V [Volume Filter](#) which can be used to filter the traversal of [Customer](#), [Media](#), [Volume](#), [Repository](#) and [Flag](#) values.
- -f Report format (default = 1).

If an argument value starts with the value `FI:`, the value for that attribute will be read from the file name specified immediately after it. For example, if a file named `ACME_volumes` has the content `ACME_*. *`, specifying `FI:/etc/ACME_volumes` will have the same effect as `-V ACME. *. *`. Using `FI:` to refer to a file for an attribute value works for all attributes.

If the pattern being matched starts with `*LIST:` then rather than matching the literal value, each record in the file specified as `*LIST:filename` will be tested. If one matches the match will succeed.

2021/06/16 02:14 · Scott Cunliffe

[include page](#)

Technical Support

The TapeTrack Software is commercially supported by a full time help desk staff.

If you are experiencing problems or want some advice on how to configure or use the product please see the [Accessing Technical Support](#) page.

Exit Statuses

1. **zero** Program has ended successfully.
2. **non-zero** Program has not ended successfully.

Environment

Files

stdout: Output Reports.
stderr: Diagnostic messages.
stdin: Program input.

Example

Zone List Report - format 1

Command line syntax

```
TMSS10ZoneList -S user:-password@server -f 1
```

Output

```

                System: TapeTrack
Report Description: Zone Inventory
Report Notes: ZoneID(1:1) Description(Drawer 1 divider 1)

Report Width: 113 bytes

Seq.      Customer
Barcode           Slot      Next Move      Media Type
-----
      1 North Carolina Data Center      LT0 Cartridge
US03.LT0.000000L5      1.1
      2 North Carolina Data Center      LT0 Cartridge
US03.LT0.000001L5      1.2
      3 North Carolina Data Center      LT0 Cartridge
US03.LT0.000002L5      1.3
      4 North Carolina Data Center      LT0 Cartridge
US03.LT0.000003L5      1.4
      5 North Carolina Data Center      LT0 Cartridge
US03.LT0.000004L5      1.5
      6 North Carolina Data Center      LT0 Cartridge
US03.LT0.000005L5      1.6
      7 North Carolina Data Center      LT0 Cartridge
US03.LT0.000006L5      1.7
      8 North Carolina Data Center      LT0 Cartridge
US03.LT0.000007L5      1.8
-----

                System: TapeTrack
Report Description: Zone Inventory
Report Notes: ZoneID(GEMTRAC1) Description(GemTrac Rack 1)

```

Report Width: 113 bytes

Seq.	Customer	Slot	Next Move	Media Type
Barcode				
1	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000001L6		1.1		
2	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000005L6		1.16	1970-01-05	
3	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000024L6		1.19		
4	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000025L6		1.20		
5	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000027L6		1.21		
6	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000028L6		1.22		
7	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000029L6		1.23		
8	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000030L6		1.24		
9	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000031L6		1.25		
10	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000032L6		1.26		
11	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000033L6		1.27		
12	Los Angeles Data Center			LT0 Cartridge
US02.LT0.000034L6		1.28		

Zone List Report - format 2 (default)

Command line syntax

```
TMSS10ZoneList -S user:-password@server -f 2
```

Output

System: TapeTrack
 Report Description: Zone Allocation
 Report Width: 112 bytes

Seq.	Customer	Media Type
------	----------	------------

Repository	Zone		
1 Los Angeles Data Center Offsite Vault	GEMTRAC1	LTO Cartridge	
2 - GEMTRAC2		-	-
3 North Carolina Data Center Offsite Vault	GEMTRAC4	LTO Cartridge	

See Also

[Command Line Utility Troubleshooting and Diagnosis](#)

Changelog

Cannot load rss feed.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/cli/tmss10zonelist>

Last update: **2025/07/04 04:34**

