


Using Lite To Move Volumes

While placing Volumes into a move is usually performed by using TapeMaster or a synchronization method, they can be moved using Lite when required.

Example Volume before move, current location in the Library Repository.



The screenshot shows the TapeTrack TapeMaster application window. The left sidebar shows a tree structure with 'GazillaByte - Pro' and 'US01 - US Data Center'. The main area has tabs for 'Inventory', 'DR Strategies', 'Data Clusters', 'Simple Management', 'Uploaded Files', and 'LTO Cartridge' (which is selected). A 'Volumes' table is displayed with the following data:

ID	Current Location	Target Location	Flags	Description
LTO123L4	Library		Cn	

Below the table, it says 'Total Items 1'. The 'Repositories' section shows three icons: 'Library' (a tape drive icon), 'Offsite Vault' (a vault icon), and 'Scratch Pool' (a recycling bin icon). At the bottom right, there is a connection status: 'Connection 127.0.0.1 uses AES 256 bit'.

Sending Volumes

Sending a Volume is the process of placing a Volume into a move status from the Repository you are currently at to that Repository's next Repository. The Next Repository is set in the Repository Options in TapeMaster.




For this example we will assume you are located at the Library in the data center. We will be placing a Volume in the Library into a move to the next Repository, the Vault. Essentially pushing the Volume into a move from where you are, to the Next repository, the vault.

Using Lites' [Send function](#), scan the required Volumes to place them into a move to the vault.



The Volumes that were scanned in the Send process will now be in a move to the Next Repository, in this example the vault.



ID	Current Location	Target Location	Flags	Description
LTO123L4	Library	Offsite Vault	CMn	

Total Items 1

Repositories

Library Offsite Vault Scratch Pool

Connection 127.0.0.1 uses AES 256 bit

Volumes, using [Lite Scan Out](#) can now be scanned out.

Recalling Volumes

While placing Volumes into a move is usually performed by using TapeMaster or a synchronization

method, they can be moved using Lite when required.

Example Volume before move, current location in the Vault Repository.

File Administration Favorites Tools View Help

Customer Filter

GazillaByte - Pro

US01 - US Da

Inventory DR Strategies Data Clusters Simple Management Uploaded Files LTO Cartridge

Volumes

ID	Current Location	Target Location	Flags	Description
Enter text h...	Enter text here	Enter text here	E...	Enter text here
LT0123L4	Offsite Vault		Cn0	

Total Items 1

Repositories

Library Offsite Vault Scratch Pool

Connection 127.0.0.1 uses AES 256 bit

Recalling a Volume is the process of placing a Volume into a move status from another Repository to the Repository you are currently at.



For this example we will assume you are located at the Scratch Rack in the data center. We will be placing a Volume into a move from its' current location, the vault, to your location, the Scratch Rack. Essentially pulling the Volume from where it is to where you are.

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://rtfm.tapetrack.com/desktop/desktop_purpose/lite_move?rev=1720575249

Last update: **2025/01/21 22:07**



