2025/12/01 11:24 1/3 Desktop Scan Window


Desktop Scan Window

Overview

The Desktop Scan Window is the common interface used by TapeTrack Desktop Programs to scan information into TapeTrack.

The window supports various scan input options, including:

- Barcode scanner,
- GazillaByte CloudScan Mobile Devices
- Keyboard
- Windows Cipboard
- File Input via Cut and Paste and Multiple File Selection.




Notes:

- A Alphanumeric display of barcode.
- **B** Scanned, or entered, display of barcode.
- C List of scanned, or entered, barcodes.
- D Options to enter barcodes including windows Clipboard, File Open, CloudScan and SCSI.
- **E** If Barcode Administration is not set to assume a Customer-ID or Media-ID for a given Volume, Defaults can be set to associate Unqualified Barcodes with a specific Customer and Media Type.
- F The Barcode Scanning Window uses sounds to verify scans. To disable this, set Enable Sounds to False.

Last update: 2025/01/21 22:07

Windows Clipboard

Copy the volume-ID/s to windows clipboard. With the Scan Out Volumes input window open (click the button with the scanner image at the top right of the window to open if required) click the paste button at the top of the window and volume ID/s will be scanned out. Click the X in the top right corner when finished scanning volumes.



File Input

With the Scan Out Volumes input window open click on the file input button {image} Open the file containing the volumes to be scanned out by clicking on the file input button at the top of the window. Locate and select the file in the browser and click open. Volumes will be loaded from the file and scanned out. Click the X in the top right corner when finished scanning volumes.




Keyboard Input

With the Scan Out Volumes input window open and in focus type in the volume/s barcode and hit enter to scan volumes from the Scan-Out list. Correct volumes scanned out will display in the lower window with an audible beep and a message "Request OK". Incorrect volumes will display in the lower window with an audible warning "The volume scanned was not in the list" and message displayed in red Scanned Volume is not in the list. Incorrect volumes scanned will not be entered into TapeTrack. Click the X in the top right corner when finished scanning volumes.

https://rtfm.tapetrack.com/ Printed on 2025/12/01 11:24

2025/12/01 11:24 3/3 Desktop Scan Window



scanning

Setting the Default Customer-ID and Medai-ID

There are two ways to set the Customer and or Media Type when in the Scan Windows.

- Manually enter the new Customer ID and Media Type in the Defaults window.
- Scan a Barcode for the new Customer and Media Type.

Barcodes starting with a period are used to set the default customer and media.

- .ACME.LTO will set the customer to ACME and the media type to LTO. .ACME will just set the customer.
- ..LTO will just set the media.

From:

https://rtfm.tapetrack.com/ - TapeTrack Documentation

Permanent link:

https://rtfm.tapetrack.com/desktop/scan window?rev=1504888203

Last update: 2025/01/21 22:07

