

# Setting TapeTrack License

## Overview

When initially installed, the TapeTrack Framework Server will allow up to 100 tape volumes using a free license. To add more than 100 volumes or operate with more than 100 volumes you will need upgrade your TapeTrack license from the free license key to either a [temporary license, 90 day trial license](#) or [permanent license](#) key.

## Temporary License

A temporary license key will allow you to operate the TapeTrack Software without restriction, but this mode of licensing is reserved for those evaluating the TapeTrack Software or those needing a license in an emergency situation. Temporary licenses are restricted to less than two weeks.

To obtain a temporary license:

1. Open TapeTrack TapeMaster and login with the user name **tapemaster** (case sensitive) and leave password blank (or use your password if it has been changed).




2. From the menu click Help → Framework Server Licensing



3. click Get temporary license and OK



4. Press **F5** while in the customer tree window to refresh new information. Your **License Status** should now display **OK** and your expiry date should now be approximately 12 days from now.



## 90 Day Trial License

To Upgrade your free license to a full evaluation license:

Open TapeTrack TapeMaster and login with the user name **tapemaster** (case sensitive) and leave password blank (or use your password if it has been changed).

From the menu click Help → Framework Server Licensing

In the TapeTrack License window change the default values to your preferred details:

### Server Details

Change Owner from ACME Corp to your company name (e.g. **GazillaByte**)

Change description value to something more relevant (e.g. **Production**)

Set Expiry Date to new expiry (e.g. 90 days from today)

### License Limits

Change Volumes to desired number (0 = unlimited)

### Exporting License

Once all changes have been made, click Apply license changes and Export license to a file to export updated license file to a known name (e.g. LicenseExport.cfg) and location.

Check the information in the config file (LicenseExport.cfg) by opening in Notepad or similar text editor and check all information has been updated and is correct. If it is not correct, delete file and repeat steps 3 to 6.

### Installing Temporary License

To allow you to start using TapeTrack until your new key is installed click Get temporary license and OK

Press **F5** while in the customer tree window to refresh new information (Company name etc.)

TapeTrack TapeMaster should now display your new **Owner** name in place of ACME and the lower right of the screen should display TapeTrack Server License is OK

## Permanent License

A permanent license key will allow you to operate the TapeTrack software without restriction until the expiry date associated with your license occurs.

Permanent license/s to TapeTrack are restricted to those who have an written End User License Agreement (EULA) with GazillaByte.

To obtain a permanent license:

From:  
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
[https://rtfm.tapetrack.com/master/set\\_license?rev=1501518066](https://rtfm.tapetrack.com/master/set_license?rev=1501518066)

Last update: **2025/01/21 22:07**

