


Adding and Updating User Information

To be able to login to a TapeTrack Framework Server, you must have a [User-ID](#) and password.

This section describes how to add a new User-ID and set attributes for that User-ID.

Group/User Administration

On the Administration drop-down menu in TapeTrack TapeMaster select Group/User Administration.



To add a new User, right-click in the white space on the User Administration screen and select Add.



To update an existing User, double-click on that User or right-click and select Properties.

The Add New User window will display six tabs:

- Identity
- Group
- IP Ranges
- Access
- Options
- Defaults

Identity

The Identity tab provides fields to update the User - ID and Name.

- User ID: The User ID will be the user name that the user uses to login to TapeTrack products.
- Name: The name is the User's desired display name.



If using windows Active Domain to log into TapeTrack, the username must match your AD username

Add New User		
Identity IP Ranges Access		
[-] Identity		
ID		
Name		
[-] Group		
ID		
[-] Options		
Administrative rights		False
Scan-In Only		False
Disabled		False
No Scanner		False
No Time-Out		False
tapemaster rights		False
Allow access inheritance		False
Certify		False
AD Domain		
Require AD Group		False
[-] Client Access		
TapeMaster		True
Lite		True
Checkpoint		False
Sync		True
[-] Details		
Email Address		
Description		
[-] Defaults		
Customer-ID		<No Selection>

Save Cancel Help

Group

The Group tab is where a User is added to a group depending on their role and access required.

- Group: Associates the selected User with a Group.
- Role: Sets the Role for the User.



Select group to assign user to from the drop-down list or [add new group](#).

IP Ranges


The IP Ranges tab sets restrictions on which IP addresses a User can access the TapeTrack Server from. To add or delete, right-click the window. Global Access (0.0.0.0) will allow access from any IP.



Access

The Access tab sets permissions for which Customers the selected User can access and how that

User can interact with Volumes in the selected Customer.




- Customer ID: Enter the Customer-ID for the Customer that the User should have access to.
 - US01 will give access to US01 only
 - US* will give access to all customers starting with US
 - * will give access to all customers
- Read: Allows the User to view but not update Volumes in the above Customer. Must be enabled for the User to be able to view Volumes in the selected Customer ID.
- Write: Allows the User to perform basic operations for Volumes in a Customer.
- Alter: Allows the User to Add and Delete Media and Volumes to the selected Customer.

Click Add.

Options

The Options tab has 3 sections to provide access to additional features of the software.



Options

In the Options section is where you can select True or False to give that User access to that feature.

- **Administrative rights:** When set to True the User will have Administration Rights with Server Administrator privileges or the ability to Add/Delete Customers and Add/Delete Media Types.
- **Scan-In Only:** When set to True the User will only be able to Scan tapes into the system.
- **Disabled:** When set to True the User's access will be in a disabled status, so that they are not able to access any TapeTrack products. This does not delete the User.
- **No Scanner:** When set to True the Barcode Scanning Window will provide an auto-complete drop-down.
- **No Time-Out:** By default, all User's are logged out of TapeMaster after ten minutes of inactivity. Setting this to True, the selected User will not time out.
- **Tapemaster rights:** When set to True, it allows the User to gain the same administrative rights as the tapemaster superuser account.
- **Certify:** Assigns the ability to [generate certificates](#).
- **AD Domain:** This is required if the User logs on to TapeTrack with their Active Directory Username and Password.
- **Require AD Group:** When set to True, the User must use their [Active Directory](#) credentials.

Client Access

- When any of the Client Access are set to True, it allows the User to have access to the TapeTrack software that is selected.


Default settings give access to TapeMaster, Lite and Sync.

Details

- Allows inclusion of user email, which may be used instead of username to log into TapeTrack directly (ie not using Active Directory).

Defaults

The Defaults tab sets a User's default Customer and Media Type for Barcode scanning. These defaults can be changed in the Barcode Scanning Window at any point.



The screenshot shows a window titled "Add New User" with a close button (X) in the top right corner. The window has several tabs: Identity, Group, IP Ranges, Access, Options, and Defaults. The "Defaults" tab is selected. Under the "Barcode Defaults" section, there are two rows of dropdown menus. The first row is for "Customer-ID", with "US01" selected for the first dropdown and "New York Data Center" selected for the second dropdown. The second row is for "Media-ID", with "LTO" selected for the first dropdown and "LTO Cartridge" selected for the second dropdown. All dropdown menus have a downward arrow on the right side.

Once all information is correct and complete click Save to create new user. Repeat instructions above to add more user-ID's or click the X at the top right corner to close the **User Administration** window.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/master/user?rev=1535327038>

Last update: **2025/01/21 22:07**

