# **Adding and Updating User Information**

To be able to login to a TapeTrack Framework Server, you must have a User-ID and password.

This section describes how to add a new User-ID and set attributes for that User-ID.

# **Group/User Administration**

On the Administration drop-down menu in TapeTrack TapeMaster select Group/User Administration.

🚺 Ta	apeTrack TapeMaster™ (GazillaByte LL	C)			3
File	Administration Favorites Tools	View Help			
	Active User List Client Licensing				(
	Barcode Administration	5/39) (326/0)	📓 Inventory 🧕 (	DR Strategies  🕕 [	) ata Clusters 🛛 🔟 Simp
	Group/User Administration	(2,319/38)	Volumes		
	Message List	nter A (121/1)			5
	Server Options		ID	Current Location	Target Location Fla
	Server Statistics		Enter text h 🝸	Enter text h 🍸	Enter text 🀇 En
	Stock Control				
	Zone Administration				Ž
		·			
	0			~~~~~	

To add a new User, right-click in the white space on the User Administration screen and select Add.

ser-ID	Name		Status		Group		Role		Email		Descri
nter text here 🏼 🖓	Enter text here	7	Enter text	7	Enter text h	7	Enter text	Y	Enter text	7	Enter
tapemaster			Active								
Add											
Delete	13										
Edit	>										
Edit Export	>										
Export	> > nent >										
Export Managem											
Export											

To update an existing User, double-click on that User or right-click and select Properties.

The Add New User window will display three tabs:

- Identity
- IP Ranges
- Access

# Identity

The Identity tab provides fields to update the:

- Identity
  - **User-ID**: The User ID will be the user name that the user uses to login to TapeTrack products.
  - **Name**: The name is the User's desired display name.
- Group
  - **Group ID**: Select group to assign user to from the drop-down list or add new group.
- Options
  - **Administrative rights**: When set to True the User will have Administration Rights with Server Administrator privileges or the ability to Add/Delete Customers and Media Types.
  - $\circ~$  Scan-In Only: When set to True the User will only be able to Scan tapes into the system.
  - **Disabled**: When set to True the User's access will be in a disabled status, so that they are not able to access any TapeTrack products. This does not delete the User.
  - **No Scanner**: When set to True the Barcode Scanning Window will provide an autocomplete drop-down.
  - **No Time-Out**: By default, all User's are logged out of TapeMaster after ten minutes of inactivity. Setting this to True, the selected User will not time out.
  - tapemaster rights: When set to True, it allows the User to gain the same

- administrative rights as the tapemaster superuser account.
- **Certify**: Assigns the ability to generate certificates.
- **AD Domain**: This is required if the User logs on to TapeTrack with their Active Directory Username and Password.
- **Require AD Group**: When set to True, the User must use their Active Directory credentials.
- Client Access
  - TapeMaster: Authorizes User-ID access to TapeMaster
  - Lite: Authorizes User-ID access to Lite
  - **Checkpoint**: Authorizes User-ID access to Checkpoint
  - **Sync**: Authorizes User-ID access to Sync software.
- Details
  - Email Address:
  - Description:
- Defaults
  - Customer-ID:



If using windows Active Domain to log into TapeTrack, the username must match your AD username

Add	New User		×
2	Identity 🔮 IP Ranges	Access	
Ξ	Identity		
	ID		
	Name		
Ξ	Group		
	ID		
Ξ	Options		
	Administrative rights	False	
	Scan-In Only	False	
	Disabled	False	
	No Scanner	False	
	No Time-Out	False	
	tapemaster rights	False	
	Allow access inheritance	False	
	Certify	False	
	AD Domain		
	Require AD Group	False	
	Client Access		
	TapeMaster	True	
	Lite	True	
	Checkpoint	False	
	Sync	True	
Ξ	Details		
	Email Address		
	Description		
Ξ	Defaults		
	Customer-ID	<no selection=""></no>	
			-
		Save Cancel Help	
		Save Cancel Help	

# **IP** Ranges

The IP Ranges tab sets restrictions on which IP addresses a User can access the TapeTrack Server from. To add or delete, right-click the window and select from the menu.

Global Access (0.0.0.0) will allow access from any IP.

Add New User		×
🧵 Identity 💉 I	P Ranges 🔒 Access	
Seq. IP 	Add IP	
	Add Global Access IF	

### Access

The Access tab sets permissions for which Customers the selected User can access and how that User can interact with Volumes in the selected Customer.

Add New User						×
Identity ✓   Customer-ID ■   Access Read   Write Alter   Alter Catalog	IP Ranges Acces	Customer-ID I US*	Access Read	Write Alter	Catalog	
Add Access Predit Customer US01 US02	<b>ction</b> Description	Access Read Read		Alter Catalo Alter Catalo		6
Total Items	2			Save	Cancel	Help

- Customer ID: Enter the Customer-ID for the Customer that the User should have access to.
  - $\circ\,$  US01 will give access to US01 only
  - $\circ~$  US\* will give access to all customers starting with US
  - $\circ$  \* will give access to all customers
- Read: Allows the User to view but not update Volumes in the above Customer. Must be enabled for the User to be able to view Volumes in the selected Customer ID.
- Write: Allows the User to perform basic operations for Volumes in a Customer.
- Alter: Allows the User to Add and Delete Media and Volumes to the selected Customer.

Click Add.

# Options

The Options tab has 3 sections to provide access to additional features of the software.

	identity 🤒 Group 🖉 Ir	Ranges 🧧 Access 者 Options 🛃 Defaul	ts			
Ξ	Options					
	Administrative rights	True				
	Scan-In Only	False				
Disabled		False				
	No Scanner	False				
	No Time-Out	False				
	tapemaster rights	True				
	Certify	True				
	AD Domain	your.tapetrack.domain				
	Require AD Group	True				
Ξ	Client Access					
	TapeMaster	True				
	Lite	True				
	Checkpoint	False				
	Sync	True				
Ξ	Details					
	Email Address					
	Description					

#### Options

In the Options section is where you can select True or False to give that User access to that feature.

- Administrative rights: When set to True the User will have Administration Rights with Server Administrator privileges or the ability to Add/Delete Customers and Add/Delete Media Types.
- Scan-In Only: When set to True the User will only be able to Scan tapes into the system.
- **Disabled**: When set to True the User's access will be in a disabled status, so that they are not able to access any TapeTrack products. This does not delete the User.
- **No Scanner**: When set to True the Barcode Scanning Window will provide an auto-complete drop-down.
- **No Time-Out**: By default, all User's are logged out of TapeMaster after ten minutes of inactivity. Setting this to True, the selected User will not time out.
- **Tapemaster rights**: When set to True, it allows the User to gain the same administrative rights as the tapemaster superuser account.
- Certify: Assigns the ability to generate certificates.
- **AD Domain**: This is required if the User logs on to TapeTrack with their Active Directory Username and Password.
- Require AD Group: When set to True, the User must use their Active Directory credentials.

#### **Client Access**

• When any of the Client Access are set to True, it allows the User to have access to the TapeTrack software that is selected.

Default settings give access to TapeMaster, Lite and Sync.

#### Details

• Allows inclusion of user email, which may be used instead of username to log into TapeTrack directly (ie not using Active Directory).

#### Defaults

The Defaults tab sets a User's default Customer and Media Type for Barcode scanning. These defaults can be changed in the Barcode Scanning Window at any point.

Add New User		×				
🧏 Identity 🧏 Gr	oup 🖉 IP Ranges 🔒 Access 📓 Options 📓 Defaults					
Barcode Defaults						
Customer-ID	Customer-ID US01 New York Data Center					
Media-ID	LTO Cartridge V					
harring and the second		<u>~</u>				

Once all information is correct and complete click Save to create new user. Repeat instructions above to add more user-ID's or click the X at the top right corner to close the **User Administration** window.

#### Troubleshooting: Add user errors

