


Technical Note: Configuration File

Modifying config file in TapeMaster and Lite to remove slot display.

Open TMSSMaster.cfg in a plain text editor such as Notepad. TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

    /*
    variables = {
        TMSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```

Remove comment tags /* & */ from above and below variables.

Change

TMSLEVELNAMES = "A,B,C";

to

TMSNOLEVELSLOT = "true";


```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
  //
  // When exporting data to email send to the following addresses
  //
  email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

  variables = {
    TMSSNOLEVELSLOT = "true";
  };

  showparent = true;
};


defaults = {
```

and save file

 Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file.


To check the modification was successful, login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below..

Before modification - displaying Zone, shelf and slot.



ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
000001L5	Rack_01 [6.1]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10.10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10.10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

After modification - displaying Zone and shelf only.



The screenshot shows the TapeTrack software interface with a navigation bar at the top containing 'Inventory', 'DR Strategies', 'Data Clusters', 'Simple Management', 'Uploaded Files', and 'Consignments'. Below this is a 'Volumes' section with a table. The table has columns for ID, Current Location, Target Location, Flags, Move Time, Due in, Container, and Next Move. The data rows are as follows:

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
000001L5	Rack_01 [6]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

Open TMSLite.cfg in Notepad

image.png

Remove comment tags /* & */ from above and below variables.

Change TMSLEVELNAMES = "A,B,C"; to TMSNOLEVELSLOT = "true";

And save file

image.png

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://rtfm.tapetrack.com/technote/config_file?rev=1528944866

Last update: **2025/01/21 22:07**

