


Remove Slot Level Display In TapeMaster

Modify the TapeMaster Configuration File

Locate the TapeMaster Configuration file (default location C:\Program Files\TapeTrack\TapeTrack TapeMaster\TMSSMaster.cfg) and open with Notepad or other plain text editor.

Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

    /*
    variables = {
        TMSSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```

Remove comment tags `/*` & `*/` from above and below variables.

Change the line of code

`TMSSLEVELNAMES = "A,B,C";`

to

`TMSSNOLEVELSLOT = "true";`

TMSSMaster.cfg - Notepad

File Edit Format View Help

```
options = {  
    //  
    // When exporting data to email send to the following addresses  
    //  
    email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];  
  
    variables = {  
        TMSSNOLEVELSLOT = "true";  
    };  
  
    showparent = true;  
};  
  
defaults = {
```

and save file.



Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file or other file extension.

To check the modification was successful:

Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below.

Before modification - TapeMaster displaying Zone, shelf and slot.

Inventory DR Strategies Data Clusters Simple Management Uploaded Files Consignments

Volumes

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6.1]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10.10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10.10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

After modification - TapeMaster displaying Zone and shelf only.

Inventory							
DR Strategies							
Data Clusters							
Simple Management							
Uploaded Files							
Consignments							
Volumes							
ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Mo
Enter text h	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter ...
000001L5	Rack_01 [6]		CNO		Unspecified	Unassigned	Perman
000002L5	Rack_01 [10]		CGNO		Unspecified	Unassigned	Perman
000003L5	Rack_03 [10]		CNO		Unspecified	Unassigned	Perman
000004L5	Library		CnN		Unspecified	Unassigned	Perman
000005L5	Library		CnN		Unspecified	Unassigned	Perman
000006L5	Library		CEnN		Unspecified	Unassigned	Perman



If when opening TapeTrack TapeMaster you receive an error - **Failed to read configuration file (TMSSMaster.cfg): Line() - Syntax error** check the configuration file that you have used plain ASCII quotes (" ") and not rich text quotes (" ") and that the replaced text is correct.

[technote](#), [config](#), [slotting](#), [tapemaster](#), [update-doco](#)

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://rtfm.tapetrack.com/technote/config_file_tapemaster/remove_slot?rev=1737497272

Last update: **2025/01/21 22:07**

