

# TapeMaster Configuration File

To modify TapeMaster, open TMSSMaster.cfg in a plain text editor such as Notepad. TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

## Remove Slot Level Display

Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

    /*
    variables = {
        TMSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```

Remove comment tags /\* & \*/ from above and below variables.

Change the line of code  
TMSLEVELNAMES = "A,B,C";  
to  
TMSNOLEVELSLOT = "true";

```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
  //
  // When exporting data to email send to the following addresses
  //
  email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

  variables = {
    TMSSNOLEVELSLOT = "true";
  };

  showparent = true;
};

defaults = {
```

and save file

To check the modification was successful:

Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below.

Before modification - TapeMaster displaying Zone, shelf and slot.

| ID       | Current Location | Target Location | Flags | Move Time | Due in      | Container  | Next Move |
|----------|------------------|-----------------|-------|-----------|-------------|------------|-----------|
| 000001L5 | Rack_01 [6.1]    |                 | CNO   |           | Unspecified | Unassigned | Permanent |
| 000002L5 | Rack_01 [10.10]  |                 | CGNO  |           | Unspecified | Unassigned | Permanent |
| 000003L5 | Rack_03 [10.10]  |                 | CNO   |           | Unspecified | Unassigned | Permanent |
| 000004L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Permanent |
| 000005L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Permanent |
| 000006L5 | Library          |                 | CEnN  |           | Unspecified | Unassigned | Permanent |

After modification - TapeMaster displaying Zone and shelf only.

Inventory DR Strategies Data Clusters Simple Management Uploaded Files Consignments

### Volumes

| ID       | Current Location | Target Location | Flags | Move Time | Due in      | Container  | Next M |
|----------|------------------|-----------------|-------|-----------|-------------|------------|--------|
| 000001L5 | Rack_01 [6]      |                 | CNO   |           | Unspecified | Unassigned | Perman |
| 000002L5 | Rack_01 [10]     |                 | CGNO  |           | Unspecified | Unassigned | Perman |
| 000003L5 | Rack_03 [10]     |                 | CNO   |           | Unspecified | Unassigned | Perman |
| 000004L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Perman |
| 000005L5 | Library          |                 | CnN   |           | Unspecified | Unassigned | Perman |
| 000006L5 | Library          |                 | CEnN  |           | Unspecified | Unassigned | Perman |

From:  
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
[https://rtfm.tapetrack.com/technote/config\\_file\\_tapemaster?rev=1530234906](https://rtfm.tapetrack.com/technote/config_file_tapemaster?rev=1530234906)

Last update: **2025/01/21 22:07**

