

# Deleting Volumes



You must have **Alter** rights to delete volumes

Select the required volume, or range of volumes from the inventory window you want to delete.

Right click highlighted volume/s and select Delete, or press Delete (DEL) on the keyboard.

The screenshot shows the 'Volumes' window in TapeMaster. The window title is 'Nashville Data Center LTO Cartridge'. The interface includes a menu bar with 'Inventory', 'DR Strategies', 'Data Clusters', 'Simple Management', and 'Uploaded Files'. Below the menu bar is a table of volumes. The table has columns: ID, Current Location, Target Location, Flags, Move Time, Due in, Container, and Next Move. A context menu is open over the table, with 'Delete' selected. The menu items are: Add, Delete, Edit, Export (Ctrl+E), Find, Favorites, Print, Properties, Select, Special Operations, and View. The table data is as follows:

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
00000113	Library		CnN		Unspecified	Unassigned	Permanent
00	Library		CDMnNt	D1:01:06:49	Unspecified	Unassigned	Tuesday,
00			CnNtZ		Unspecified	Unassigned	Permanent
00			CnNtZ		Unspecified	Unassigned	Permanent
00	Library		CMnNtZ	D4:03:08:46	Unspecified	Unassigned	Permanent
00			CnN		Unspecified	Unassigned	Permanent
00			CnNt		Unspecified	Unassigned	Permanent
00			CnNOT		Unspecified	Unassigned	Permanent
00			CnNOT		Unspecified	Unassigned	Permanent
00	Library		CMnNZ	D4:03:08:46	Unspecified	Unassigned	Permanent
00	Library		CMnZ	D4:03:08:46	Unspecified	Unassigned	Permanent
00	Library		CMnZ	D4:03:08:46	Unspecified	Unassigned	Permanent
00	Library		CMnZ	D4:03:08:46	Unspecified	Unassigned	Permanent
00	Library		CMnZ	D4:03:08:46	Unspecified	Unassigned	Permanent

The **Volume Deletion** window will display the **Repositories** where the volumes to be deleted are located in the top pane and Volume-ID's in the lower pane.



If the **Volume Deletion** window is not displayed it is because you are running an outdated version of TapeMaster. Instructions to delete volumes in older versions of TapeMaster can be found [here](#)

### Volume Deletion

You have selected Volumes for deletion from the following Repositories.

If one of those Repositories does not allow deletes, you must either allow deletes, or remove the Volumes from that Repository.

The Volumes in a Repository can be removed from the deletion list below by selecting the Repository and selecting the action from the Context Menu.

Repositories with Volumes to be deleted		
Repository	Count	Delete Allowed
Offsite Vault	1	Deletes allowed
Library	1	Deletes allowed

List contains 2 records


Volumes to be deleted
000001L3
000008L6

List contains 2 records


Each row in the top pane will, along with the repository description (or ID), list the number of volumes for deletion and the delete status of either **Deletes Allowed** or **Deletes Forbidden**.

For any repository listed with a status of **Deletes Forbidden** you must either:


- Right clicking the row and selecting Allow to change status to **Deletes Allowed**
- Right clicking the row and selecting Remove to remove the volumes before deletion of any volumes located in a repository with **Deletes Allowed** status.




Click Delete Volumes and Yes to the delete confirmation to delete the volumes.




As deleting volumes is permanent, clicking No to the delete confirmation is your last opportunity to cancel the delete function.

 When a volume is deleted its historical entries remain in the database. If a deleted Volume is added back in to the database, all previous history records including when deleted and added back, are listed under that volumes History tab.



When a **Volume** is deleted its historical entries remain in the database. If a deleted **Volume** is added back into the database, all previous history records including when deleted and added back, are listed under that **Volumes** History tab.

As setting **Repository** to **Allow Deletes** alters the properties of that **Repository**, if required, reset the **Repository** to **no deletes** by right-clicking the required **Repository**, selecting **Properties** and change the **Allow Deletes** field in the **Options** tab to false.



[technote](#), [volumes](#), [delete](#), [master](#)

From:  
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
[https://rtfm.tapetrack.com/technote/delete\\_volumes?rev=1627959799](https://rtfm.tapetrack.com/technote/delete_volumes?rev=1627959799)

Last update: **2025/01/21 22:07**

