

Setting A Password


There are several reasons to set or change passwords in TapeTrack such as restricting unauthorized access, good security practices or re-instating disabled user.

As a password is a secure login credential to access TapeTrack, best password practices should be employed when setting or changing user passwords.

If using Active Directory authentication, local TapeTrack passwords will not be referenced when a user logs in (with No MD5 box checked on login screen) but can be used to reset access when a user account has been disabled or revoked.

Changing A Password For Current User

Open the password utility by selecting File → Reset Password from the main menu.



Setting Your Own Password

In the **Password change** window, enter:

- your current password
- new password
- verify new password



Click OK to update your password and return you to TapeMaster.

Randomly Generate Password

Click the Random button to enter a randomly generated password into the password fields. This will also open a Random Password Set window displaying the password value. To aid you recording this

password value, you have the options:

- Click the Copy password button to copy generated password to your clipboard.
- Clicking the Copy message button will give you the text “ A new TapeTrack User-ID has been created for you to use. You can access this account using the User-ID (Current User) and the password(B@7NpJ%7GR)” copied to your clipboard for convenience when sending a message to the user with login details.
- Clicking the Email message button will open up your default email client with the same text as Copy message.

Click OK to close the Random Password Set window.



Enter your current password in the Current Password field.

Click OK to update your password and close the Password Change window.

Changing Other Users Passwords



If the menu option **Administration** is greyed out and inaccessible, you do not have sufficient privileges (tapemaster rights) to change others passwords

From the main menu select Administration → Group/User Administration.


The screenshot shows the TapeTrack TapeMaster™ (GazillaByte) application window. The interface includes a menu bar (File, Administration, Favorites, Tools, View, Help) and a Customer Filter. The left sidebar displays a tree view of the production environment, including 'GazillaByte - Production', 'US00 - United State', 'US01 - New York', 'US02 - Los Angel', 'CONT - Conta', 'LTO - LTO Car', and 'US03 - North Car'. The main area is titled 'Volumes' and shows a table of data for the 'Los Angeles Data Center' using 'LTO Cartridge'. The table has columns for ID, Current Location, Target Location, Next Move, and Description. Below the table, it indicates 'Total Items 1,585'. At the bottom, there is a 'Repositories' section with icons for Gemtrac, Library, Transport, and Offsite Vault. A status bar at the bottom right shows 'Connection 127.0.0.1 uses AES 256 bit encryption'.

ID	Current Location	Target Location	Next Move	Description
000000L6	Offsite Vault	Library	Permanent	
000001L6	Library	Offsite Vault	Permanent	
000002L6	Library	Offsite Vault	Permanent	
000003L6	Library		Permanent	
000004L6	Library		Permanent	
000005L6	Library	Offsite Vault	Permanent	
000006L6	Library	Offsite Vault	Permanent	
000007L6	Library	Offsite Vault	Permanent	
000008L6	Library		Permanent	
000009L6	Library		Permanent	
000010L6	Library		Permanent	
000011L6	Offsite Vault		Permanent	
000012L6	Library		Permanent	
000013L6	Library		Permanent	
000014L6	Library		Permanent	
000015L6	Library		Permanent	
000016L6	Offsite Vault	Library	Permanent	
000017L6	Offsite Vault	Library	Permanent	

Right click on the required User-ID and select from the popup menu, Management → Reset Password to open the **Password Change** window.




If you don't see the Management menu when right clicking on a User-ID, please see [Previous releases method](#) for resetting passwords



In the Password Change window to set a known password value, insert new password in the New Password field.

Type password in the Password (again) field to confirm the password value.



Alternatively, if you would like to set a randomly generated password click the Random button to enter a randomly generated password into the password fields. This will also open a Random Password Set window displaying the password value. To aid you recording this password value, you have the options:

- Click the Copy password button to copy generated password to your clipboard.
- Clicking the Copy message button will give you the text " A new TapeTrack User-ID has been created for you to use. You can access this account using the User-ID (Current User) and the password(B@7Npj%7GR)" copied to your clipboard for convenience when sending a message to the user with login details.
- Clicking the Email message button will open up your default email client with the same text as Copy message.

Click OK to close the Random Password Set window.



Click OK to close the Password Change window and return to the "User Administration" window. Update any other User's if required, click X" at the top right of the window to exit back to TapeMaster.

It is a good practice to have any user you change the password for to have them [reset](#) their password the next time they logon.

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
<https://rtfm.tapetrack.com/technote/password?rev=1784080022>

Last update: **2026/07/15 01:47**

