

User Access Rights

User access rights, or privileges, for TapeTrack are divided into software rights and Customer access. This allows the same software privileges to be assigned to different Users while also choosing which Customers they have access to.


User Rights

User rights assign access rights for the TapeTrack software menus and functions.

Administration Rights

Administration Rights allow a user-ID to:


- Set Allow Deletes for Volumes to true or false
- Add and delete Repositories
- Add and delete Media Types
- Add and delete Customers
- Set Customer options
- Set Media options
- Set Repository options



Section	Option	Value
Identity	ID	
	Name	
Group	ID	
	Options	
Options	Administrative rights	False
	Scan-In Only	False
	Disabled	False
	No Scanner	False
	No Time-Out	False
	tapemaster rights	False
	Allow access inheritance	False
	Certify	False
	AD Domain	
	Require AD Group	False

Scan-In Only

Scan-In Only restrict the user-ID to only being able to Scan-in the Volumes to their Target location.



Tapemaster Rights

tapemaster rights give the user-ID tapemaster super rights (full administration and total access) which allow:

- Access to the Administration main menu functions
- Add, Delete or disable user-ID's
- Active [Users](#)
- Barcode administration
- [User](#) administration
- Server options and statistics
- Stock Control
- Zone administration
- Server Licensing

Certify Rights


Certify rights allow a user-ID to create and read certificates.

Client Access rights determine which desktop software the user-ID has access to. The access rights are for TapeMaster, Lite, Checkpoint and Sync.

Customer Access Rights


[Customer](#) access rights can be assigned to a [User](#) on a per [Customer](#) basis. For example you may assign full [Customer](#) access to a staff member at the location of that [Customer Volumes](#) but only read access for other [Customers Volumes](#).

The Customer-ID needs to be added, not shown in images as Customer-ID's are unique to every installation. If access to all Customer-ID's is required use an asterisk as a wildcard. Once access rights have been set, click Add to commit the data. This process can be repeated for each Customer-ID required.



Read Access


Read access allows the **User-ID** to view the Inventory for the assigned **Customer-ID** but not make any alterations to the data including the **Volume's** location or attributes.



Write Access

Write access allows the [User-ID](#) to:


- Place [Volumes](#) into a move
- Confirm [Volumes](#) into Repositories
- Add or change [Volume](#) attributes and Flags



Alter Access


Alter access allows the [User-ID](#) to:

- Add [Volumes](#)
- Delete [Volumes](#) if current Repository set to Allow Deletes




Catalog Access

Catalog access allows the [User-ID](#) to access Catalog information



[technote](#), [tapemaster](#), [lite](#), [command line](#), [sync](#), [update doco](#)



From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://rtfm.tapetrack.com/technote/user_rights?rev=1651721127

Last update: **2025/01/21 22:07**

