

Adjusting Slot Allocation

From time to time you may need to adjust a [Customers Slot](#) allocation based on increased or decreased [Volume](#) numbers.

Increasing Slot Allocation

Slotting allocation can be increased by either adding extra [zones](#) to the [Repository](#), or by increasing the [Slot](#) allocation within the currently assigned [zones](#).

Decreasing Slot Allocation

Removing Empty Slots

Decreasing [Slot](#) allocation for a [Customer](#) can be as simple as reducing the [Slots](#) allocated through the [Slot Edit Range Information](#) window, as long as the [Slots](#) being removed are sequential and unoccupied.

Removing Occupied Slots


If the [Slots](#) to be removed from allocation are currently occupied, completely or partially, the [Volumes](#) will need to be reslotted before this can be accomplished.




You must have enough empty [Slots](#) under the highwater mark to accommodate any [Volumes](#) currently slotted above the mark.

To remove these [Volumes](#) from the occupied [Slots](#):

- Right click the required [Repository](#) and select [Properties](#), or double click the [Repository](#) , and click on the [Options](#) tab.



- Set Highwater Offset to the number you wish to lower Slot allocation by. For example if you currently have 3000 Slots allocated and wish to reduce the allocation to 1000 Slots set the highwater offset to 2000 (3000 - 2000).



- Run the slotting program [TMSS10SlotAllocation](#) to re-slot any Volumes above the highwater mark.
- Decrease the slot allocation.

Edit Range Information

Zone Selection

Zone-ID: **2:2** Drawer 2 divider 2

Slot Start: 1 Level 01, Slot S01

Slot End: 2000 Level 100, Slot S20

Slot Total: 2000

Slots/Level: 20

Slot Ranges

Start Slot: 1 Level/Slot: 1 1

End Slot: 1000 Level/Slot: 50 20

Total Slots: 1000

OK Cancel

| C-ID | M-ID | R-ID | Start | Slot | End |
|------|------|------|--------------------|------|---------------------|
| US03 | LTO | OFFS | Level 01, Slot S01 | 1 | Level 100, Slot S20 |

- Adjust the **Highwater Offset** back to zero to enable use of all allocated Slots.

Edit Repository: Offsite Vault

Identity Zones Slot Usage Options Usage History Movement History Certification

| | |
|--|----------|
| Allow Deletes | False |
| Allow Overlaps | False |
| De-assign from Container | False |
| Empty Container | False |
| Do not slot if Container | False |
| Do not slot | False |
| Require Tag | False |
| Require Tag Reset | False |
| No re-move | False |
| Disallow backward next move date changes | False |
| Reset Data Cluster | False |
| Confirm Container Contents | False |
| Move Container Contents | False |
| Late Threshold | 0 |
| Highwater Offset | 0 |
| Movement Mode | None |
| Next Repository | Library |
| Enable Slotting | True |

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/adjusting_slot_allocation?rev=1638831919

Last update: **2025/01/21 22:07**

