Adding and Maintaining a Zone

A Zone is a TapeTrack Object which represents a physical storage location.

Once created a Zone is then mapped to a Repository to track where volumes are allocated to a storage rack and slot number.

Adding a Zone

From the Main Menu, select Administration→Zone Administration.

М Т	ImageTrack TapeMaster™ (GazillaByte LLC)									
File	Administration	Favorites	Tools	View	Help					2
	Active User List Client Licensing Barcode Administration Group/User Administration Message List Server Options			7/39) (326/0) (2,319/38) nter A (122/1)		Inventory OR Strategies (Data Clusters C S Volumes ID Current Location Target Locati				
	Server Statistics Stock Control						Enter text n	ΎE	nter text here Y	Enter text here
	Zone Administrat	tion	~~]		-0			~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~	

From the Zone Tab, click in the Zone List Window, and then Right click to select Add from the Context Menu.

Zone Administr	ation				
1 🙆 Zones	🔍 Zone Usage				
Index ID		Description	S	lots/Level	
Enter te 🍸 En'	er text here	7 Enter text here	7 E	nter text here	7
	_	_			
Add					
Add Disab Edit	le 🔓				
Add Disat Edit Enab	le ,				
Add Disab Edit Enab Print	le > e				
Add Disat Edit Enab Print Prop	le > e >				

The Identity Tab

Identity tab the Zone properties:

- **Zone ID** Assignable ID for the Zone (1 to 10 alphanumeric characters).
- Zone description Long form description of the Zone (0 to 20 alphanumeric characters).
- Total number of slots Total number of slots that the Zone contains.
- Number of slots per row (optional) Number of slots in each row of the Zone.
- **Customer filter (optional)** Limits which Customers will see the specific Zone when assigning Zones to a Repository.

New Zone		×
Identity		
Attributes		
Index	0	
	✓ Active	
ID	GEMTRAC1	
Description	GemTrac Rack 1	
Slot Range	1 🔹 to 450 🔹 = 450	
Slots/Level	45 🜩	
Customer Filter	US03	
~		

Once all values have been entered click Save.

Associated Instructions

Once created, Zones can be then be mapped to one or more Repositories.

Maintaining a Zone

From the Main Menu, select Administration→Zone Administration.

Т	M TapeTrack TapeMaster™ (GazillaByte LLC)									
File	Administration	Favorites	Tools	View	Help					
	Active User List Client Licensing Barcode Administration Group/User Administration Message List Server Options Server Statistics			7/39) (326/0) (2,319/38) nter A (122/1) ID Current Location T Enter text h Y					ta Clusters 🔽 Sing Target Location	
	Zone Administrat	tion N								
	~		~	~		,~~		~\		

From the **Zone Administration** window right click the required zone and select Properties or double click the **zone index** number.

Zone Administration		
▲ Zones Q Zone Usage		
Index ID	Description	Slots/Level
Enter te 🍸 Enter text here 🍸	Enter text here	Enter text here
@ 00001 CT1	GemTrack 1	45
@ 00002 Add	GemTrack 2	45
@ 0000: Disable	GemTrack 3	45
@ 00004 Edit >	GemTrack 4	45
Enable		
Print >		
Properties		

Identity

Zone Usage

Ec	lit Zone									×
	Identity	Zon	e Usage							
	Custo	mer	Media	Repository	Start	End	Total	Notes	Utilization	
	Ent	7	E., 🍸	Ente 🍸	E. 🍸	E 🍸	E. 🍸	E 🍸	Enter text here	7
	😹 US	02	LTO	OFFS	1	450	450		Occupied(15) / Total(450) = 3%. Free(435)	
L	m _	~~~~	- ~~	~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~~			~~~~	~~~~	man _ man man	\sim



Last update: 2025/01/21 22:07