


# Adding and Maintaining a Zone

A **Zone** is a **TapeTrack Object** which represents a physical storage location.


Once created a Zone is then mapped to a **Repository** to track where volumes are allocated to a storage rack and slot number.

## Adding a Zone

From the Main Menu, select Administration→Zone Administration.




From the Zone Tab, click in the Zone List Window, and then Right click to select Add from the Context Menu.



## The Identity Tab

Identity tab the Zone properties:

- **Zone ID** Assignable ID for the Zone (1 to 10 alphanumeric characters).
- **Zone description** Long form description of the Zone (0 to 20 alphanumeric characters).
- **Total number of slots** Total number of slots that the Zone contains.
- **Number of slots per row (optional)** Number of slots in each row of the Zone.
- **Customer filter (optional)** Limits which [Customers](#) will see the specific Zone when assigning Zones to a [Repository](#).



The screenshot shows a 'New Zone' dialog box with an 'Identity' tab. The 'Attributes' section contains the following fields:

- Index: 0
- Active:
- ID: GEMTRAC1
- Description: GemTrac Rack 1
- Slot Range: 1 to 450 = 450
- Slots/Level: 45
- Customer Filter: US03


Once all values have been entered click Save.

## Associated Instructions


Once created, Zones can be then be [mapped](#) to one or more [Repositories](#).

## Maintaining a Zone

From the Main Menu, select Administration→Zone Administration.



From the **Zone Administration** window right click the required zone and select Properties or double click the **zone index** number.



## Identity

## Zone Usage

The **Zone Usage** tab displays information about the current usage. This information includes:

- Customer number
- Media type
- Repository mapping
- Start and end slot numbers and total number of slots
- Current utilization of slots including
  - number of used slots
  - number of free slots
  - % of used slots

### Edit Zone

Identity    Zone Usage

Customer	Media	Repository	Start	End	Total	Notes	Utilization
Ent... <input type="text"/>	E.. <input type="text"/>	Ente... <input type="text"/>	E. <input type="text"/>	E. <input type="text"/>	E. <input type="text"/>	E.. <input type="text"/>	Enter text here <input type="text"/>
US02	LTO	OFFS	1	450	450		Occupied(15) / Total(450) = 3%. Free(435)

From:  
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:  
[https://rtfm.tapetrack.com/master/admin\\_zone?rev=1507508658](https://rtfm.tapetrack.com/master/admin_zone?rev=1507508658)

Last update: **2025/01/21 22:07**

