

# Zone Administration

Zone Administration gives you access to the zone administration window, from which you can add, remove or alter current zones as well as view slots currently in use through the zone usage tab.

To access the Zone Administration window, from the main menu, select Administration → Zone Administration.



Only users with tapemaster rights have access to the Administrative menu.

## Zone Tab

The Zone tab displays current zones index, zone ID's, descriptions and number of slots per level.



The screenshot shows a window titled "Zone Administration" with two tabs: "Zones" and "Zone Usage". The "Zones" tab is active, displaying a table with the following data:

| Index | ID  | Description | Slots/Level |
|-------|-----|-------------|-------------|
| 00001 | GT1 | GemTrac 1   | 45          |
| 00002 | GT2 | GemTrac 2   | 45          |
| 00003 | GT3 | GemTrac 4   | 45          |
| 00004 | GT4 | GemTrac 4   | 45          |


## Zone Tab Right Click Options

- **Add**: Adds a new zone.
- **Disable**: Disables the use of the zone.
- **Edit**
  - **Paste (Using Selected Attributes)**
- **Enable**: Enables the use of the zone.
- **Print**
  - **All**: Prints all zones and associated information.
  - **Labels**: Prints labels for use when scanning volumes into zones.
  - **Selected**: Prints selected zones and associated information.
- **Properties**: Opens **Edit Zone** window to edit zone properties and view zone usage information.

# Zone Usage Tab


The Zone Usage tab displays the current zone index, zones ID's, Descriptions, assigned Customer and Media and Repository ID's, start and end and total slot numbers, notes, number of used slots, number of free slots and percentage of free slots.

To view the zone usage data, select the Zone Usage tab and click Yes to the **Resolve Free Slots** popup.



Data in the columns can be displayed in ascending or descending order by clicking the column headings.

Displayed data can be filtered by using the TapeTrack [String Filters](#)



The screenshot shows the "Zone Administration" window with the "Zone Usage" tab selected. It displays a table with columns for ZoneID, Zone, Description, Customer, Media, Repository, Start, End, Total, Notes, Used, Free, and %-Free. The table contains three rows of zone data and a total row.


| ZoneID | Zone | Description | Customer | Media | Repository | Start | End | Total | Notes | Used | Free  | %-Free |
|--------|------|-------------|----------|-------|------------|-------|-----|-------|-------|------|-------|--------|
| 00003  | GT3  | GemTrac 4   | US04     | LTO   | OFFS       | 1     | 450 | 450   |       | 8    | 442   | 98.22% |
| 00002  | GT2  | GemTrac 2   | US04     | LTO   | OFFS       | 1     | 450 | 450   |       | 5    | 445   | 98.89% |
| 00001  | GT1  | GemTrac 1   | US04     | LTO   | OFFS       | 1     | 450 | 450   |       | 4    | 446   | 99.11% |
| Total  |      |             |          |       |            |       |     | 1,350 |       | 17   | 1,333 | 98.74% |

Selected zones can be printed by right clicking highlighted zones and selecting Print → Selected, or Print → All to print all zones.

| ZoneID | Zone  | Description | Customer | Media | Repository | Start | End | Total | Notes | Used | Free  | %-Free |
|--------|-------|-------------|----------|-------|------------|-------|-----|-------|-------|------|-------|--------|
| 00001  | GT1   | GemTrac 1   | US04     | LTO   | OFFS       | 1     | 450 | 450   |       | 4    | 446   | 99.11% |
| 00     | Print |             | US04     | LTO   | OFFS       | 1     | 450 | 450   |       | 5    | 445   | 98.89% |
| 00003  | GT3   |             | US04     | LTO   | OFFS       | 1     | 450 | 450   |       | 8    | 442   | 98.22% |
| Total  |       |             |          |       |            |       |     | 1,350 |       | 17   | 1,333 | 98.74% |


To export to a file, select the required **Zone ID's** from the Zone Usage tab and press **Ctrl + e**.

If no zones are selected when **Ctrl + e** is pressed, a popup is presented. Click **Yes** to export all records or click **No** to exit export and select required records before pressing **Ctrl + e** to start export process.



Select the output format from:

- Comma Delimited File (CSV)
- Microsoft Excel
- Text File
- XML File



By default the **Open file when export is complete** is checked, uncheck if you do not want the file to open on export.

Click OK to export or Cancel to abort the process.

Click the X in the top right corner to exit.

### Example

Data exported to text file

```

System: TapeTrack
Report Description: Export
Production Time: Friday, June 15, 2018 - 11:16:02 (AUS Eastern Standard Time)
Report Width: 90 bytes
ZoneID Zone Description Customer Media Repository Start End Total Notes Used
Free %-Free
-----
00003 GT3 GemTrac 4 US04 LTO OFFS 1 450 450 8
442 98.22
00002 GT2 GemTrac 2 US04 LTO OFFS 1 450 450 5
445 98.89
00001 GT1 GemTrac 1 US04 LTO OFFS 1 450 450 4
446 99.11
Total 1,333 98.74 1,350 17
-----

```

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: [https://rtfm.tapetrack.com/master/admin\\_zone\\_admin?rev=1529589471](https://rtfm.tapetrack.com/master/admin_zone_admin?rev=1529589471)

Last update: **2025/01/21 22:07**

