

# Location Auto Swap

The **Location Auto Swap** allows you to display the zone, draw and slot number (absolute location) rather than the default slot number (relative location) for each of the slotted **volumes** in the inventory window.

The default settings display slot numbers for each slotted volume.

Selecting a **volume** and hitting the backspace key will change the display for that volume to zone, drawer and slot.


ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next M
Enter text h...	Enter text here	Enter text ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter
000001L3	GEMTRAC1 [1.1]		CNOT	Unspecified	Unassigned	Permanent	
000002L5	Offsite Vault [000004]		CDGNOT	Unspecified	Unassigned	Friday	
000003L5	Offsite Vault [000003]		CNOTZ	Unspecified	Unassigned	Permanent	
000004L6	Offsite Vault [000007]		CNOTZ	Unspecified	Unassigned	Permanent	
000005L6	Offsite Vault [000009]		CNOTZ	Unspecified	Unassigned	Permanent	
000006L6	Offsite Vault [000013]		CNOT	Unspecified	Unassigned	Permanent	
000007L6	Offsite Vault [000016]		CNOT	Unspecified	Unassigned	Permanent	
000008L6	Offsite Vault [000022]		CNOT	Unspecified	Unassigned	Permanent	
000009L6	Offsite Vault [000030]		CDNOT	Unspecified	Unassigned	Saturday	

Enabling the **Location Auto Swap** in the main preference's **Options** window (File → Preferences ) and setting the **Location Auto Swap Max** number above the current inventory count (eg if you have 10,000 set the value higher to 20,000) will set the display to zone, draw and slot number as the default setting.

Disable sounds	True
Show hidden Customers	True
Show hidden Media	True
Show hidden Volumes	True
Parent/Child	False
Anonymous Customers	False
Enable Consignment Tab	True
Repository-ID filters	True
Disable Volume List inline edit	False
Location Auto Swap	True
Location Auto Swap Max	100

Once the **Location Auto Swap Max** has been enabled and saved, pressing F5 in the inventory window will update the display.

Selecting a **volume** and hitting the backspace key will change the display for that volume to slot number.



ID	Current Location	Target L...	Flags	Move Time	Due in	Container	Next Mo
Enter text h...	Enter text here	Enter ...	Enter ...	Enter t...	Enter t...	Enter t...	Enter t...
000001L3	Offsite Vault [000001]	CNOT	Unspecified	Unassigned	Permanent		
000002L5	GEMTRAC1 [1.4]	CDGNOT	Unspecified	Unassigned	Friday, A		
000003L5	GEMTRAC1 [1.3]	CNOTZ	Unspecified	Unassigned	Permanent		
000004L6	GEMTRAC1 [1.7]	CNOTZ	Unspecified	Unassigned	Permanent		
000005L6	GEMTRAC1 [1.9]	CNOTZ	Unspecified	Unassigned	Permanent		
000006L6	GEMTRAC1 [1.13]	CNOT	Unspecified	Unassigned	Permanent		
000007L6	GEMTRAC1 [1.16]	CNOT	Unspecified	Unassigned	Permanent		
000008L6	GEMTRAC1 [1.22]	CNOT	Unspecified	Unassigned	Permanent		
000009L6	GEMTRAC1 [1.30]	CDNOT	Unspecified	Unassigned	Saturday		



If the **volume** count exceeds the maximum set in the **Location Auto Swap Max** field, the display will revert to the original default setting of slot number.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

[https://rtfm.tapetrack.com/master/location\\_swap](https://rtfm.tapetrack.com/master/location_swap)

Last update: **2025/01/21 22:07**

