


Location Auto Swap

The **Location Auto Swap** allows you to display the zone, draw and slot number (absolute location) rather than the default slot number (virtual location) for each of the slotted volumes in the inventory window.

The default settings display slot numbers for each slotted volume.

Selecting a volume and hitting the backspace key will change the display for that volume to zone, drawer and slot.




The screenshot shows a software interface with a menu bar containing 'Inventory', 'DR Strategies', 'Data Clusters', 'Simple Management', 'Uploaded Files', and 'Consignments'. Below the menu is a section titled 'Volumes' containing a table. The table has columns for ID, Current Location, Target Location, Flags, Move Time, Due in, Container, and Next Move. The first row is highlighted in blue and shows ID '000001L3', Current Location 'GEMTRAC1 [1.1]', and Flags 'CNOt'. A mouse cursor is pointing at the 'GEMTRAC1 [1.1]' text.

| ID | Current Location | Target Location | Flags | Move Time | Due in | Container | Next Move |
|----------|------------------------|-----------------|-------|-----------|-------------|------------|-----------|
| 000001L3 | GEMTRAC1 [1.1] | | CNOt | | Unspecified | Unassigned | Perma |
| 000002L5 | Offsite Vault [000004] | | CDGNt | | Unspecified | Unassigned | Friday |
| 000003L5 | Offsite Vault [000003] | | CNOtZ | | Unspecified | Unassigned | Perma |
| 000004L6 | Offsite Vault [000007] | | CNOtZ | | Unspecified | Unassigned | Perma |
| 000005L6 | Offsite Vault [000009] | | CNOtZ | | Unspecified | Unassigned | Perma |
| 000006L6 | Offsite Vault [000013] | | CNOt | | Unspecified | Unassigned | Perma |
| 000007L6 | Offsite Vault [000016] | | CNOt | | Unspecified | Unassigned | Perma |
| 000008L6 | Offsite Vault [000022] | | CNOt | | Unspecified | Unassigned | Perma |
| 000009L6 | Offsite Vault [000030] | | CDNOt | | Unspecified | Unassigned | Saturd |

Enabling the **Location Auto Swap** in the main preference's Options window and setting the **Location Auto Swap Max** number above the current inventory count will set the display to zone, draw and slot number as the default setting.

Selecting a volume and hitting the backspace key will change the display for that volume to slot number.



The screenshot shows the same software interface as above, but the 'Current Location' for the first row (ID '000001L3') is now 'Offsite Vault [000001]'. The mouse cursor is still pointing at this text.

| ID | Current Location | Target L... | Flags | Move Time | Due in | Container | Next Mo |
|----------|------------------------|-------------|-------|-----------|-------------|------------|-----------|
| 000001L3 | Offsite Vault [000001] | | CNOt | | Unspecified | Unassigned | Permane |
| 000002L5 | GEMTRAC1 [1.4] | | CDGNt | | Unspecified | Unassigned | Friday, A |
| 000003L5 | GEMTRAC1 [1.3] | | CNOtZ | | Unspecified | Unassigned | Permane |
| 000004L6 | GEMTRAC1 [1.7] | | CNOtZ | | Unspecified | Unassigned | Permane |
| 000005L6 | GEMTRAC1 [1.9] | | CNOtZ | | Unspecified | Unassigned | Permane |
| 000006L6 | GEMTRAC1 [1.13] | | CNOt | | Unspecified | Unassigned | Permane |
| 000007L6 | GEMTRAC1 [1.16] | | CNOt | | Unspecified | Unassigned | Permane |
| 000008L6 | GEMTRAC1 [1.22] | | CNOt | | Unspecified | Unassigned | Permane |
| 000009L6 | GEMTRAC1 [1.30] | | CDNOt | | Unspecified | Unassigned | Saturday |



If the volume count exceeds the maximum set, the display will revert to the original default setting of slot number.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://rtfm.tapetrack.com/master/location_swap?rev=1522973430

Last update: **2025/01/21 22:07**

