


Location Auto Swap

The **Location Auto Swap** allows you to display the zone, draw and slot number (absolute location) rather than the default slot number (virtual location) for each of the slotted volumes in the inventory window.

The default settings display slot numbers for each slotted volume.


Selecting a volume and hitting the backspace key will change the display for that volume to zone, drawer and slot.



| ID | Current Location | Target Location | Flags | Move Time | Due in | Container | Next M... |
|----------|------------------------|-----------------|--------|-------------|------------|-----------|-----------|
| ID | Current Location | Target Location | Flags | Move Time | Due in | Container | Next M... |
| 000001L3 | GEMTRAC1 [1.1] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000002L5 | Offsite Vault [000004] | | CDGNOT | Unspecified | Unassigned | Friday | |
| 000003L5 | Offsite Vault [000003] | | CNOTZ | Unspecified | Unassigned | Permanent | |
| 000004L6 | Offsite Vault [000007] | | CNOTZ | Unspecified | Unassigned | Permanent | |
| 000005L6 | Offsite Vault [000009] | | CNOTZ | Unspecified | Unassigned | Permanent | |
| 000006L6 | Offsite Vault [000013] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000007L6 | Offsite Vault [000016] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000008L6 | Offsite Vault [000022] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000009L6 | Offsite Vault [000030] | | CDNOT | Unspecified | Unassigned | Saturday | |

Enabling the **Location Auto Swap** in the main preference's Options window and setting the **Location Auto Swap Max** number above the current inventory count will set the display to zone, draw and slot number as the default setting.

Selecting a **volume** and hitting the backspace key will change the display for that volume to slot number.




| ID | Current Location | Target L... | Flags | Move Time | Due in | Container | Next M... |
|----------|------------------------|-------------|--------|-------------|------------|-----------|-----------|
| ID | Current Location | Target L... | Flags | Move Time | Due in | Container | Next M... |
| 000001L3 | Offsite Vault [000001] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000002L5 | GEMTRAC1 [1.4] | | CDGNOT | Unspecified | Unassigned | Friday, A | |
| 000003L5 | GEMTRAC1 [1.3] | | CNOTZ | Unspecified | Unassigned | Permanent | |
| 000004L6 | GEMTRAC1 [1.7] | | CNOTZ | Unspecified | Unassigned | Permanent | |
| 000005L6 | GEMTRAC1 [1.9] | | CNOTZ | Unspecified | Unassigned | Permanent | |
| 000006L6 | GEMTRAC1 [1.13] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000007L6 | GEMTRAC1 [1.16] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000008L6 | GEMTRAC1 [1.22] | | CNOT | Unspecified | Unassigned | Permanent | |
| 000009L6 | GEMTRAC1 [1.30] | | CDNOT | Unspecified | Unassigned | Saturday | |



If the volume count exceeds the maximum set, the display will revert to the original default setting of slot number.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**



Permanent link:

https://rtfm.tapetrack.com/master/location_swap?rev=1522974041

Last update: **2025/01/21 22:07**