


Location Auto Swap


The **Location Auto Swap** allows you to display the zone, draw and slot number (absolute location) rather than the default slot number (virtual location) for each of the slotted **volumes** in the inventory window.

The default settings display slot numbers for each slotted volume.

Selecting a **volume** and hitting the backspace key will change the display for that volume to zone, drawer and slot.




Enabling the **Location Auto Swap** in the main preference's **Options** window (File → Preferences") and setting the **Location Auto Swap Max** number above the current inventory count will set the display to zone, drawer and slot number as the default setting.




Once the **Location Auto Swap Max** has been enabled and saved, pressing F5 in the inventory window will update the display.

Selecting a **volume** and hitting the backspace key will change the display for that volume to slot number.



| ID | Current Location | Target L... | Flags | Move Time | Due in | Container | Next Mo... |
|----------|------------------------|-------------|--------|-------------|------------|-----------|------------|
| 000001L3 | Offsite Vault [000001] | | CNOT | Unspecified | Unassigned | Permane | |
| 000002L5 | GEMTRAC1 [1.4] | | CDGN0t | Unspecified | Unassigned | Friday, A | |
| 000003L5 | GEMTRAC1 [1.3] | | CN0tZ | Unspecified | Unassigned | Permane | |
| 000004L6 | GEMTRAC1 [1.7] | | CN0tZ | Unspecified | Unassigned | Permane | |
| 000005L6 | GEMTRAC1 [1.9] | | CN0tZ | Unspecified | Unassigned | Permane | |
| 000006L6 | GEMTRAC1 [1.13] | | CN0t | Unspecified | Unassigned | Permane | |
| 000007L6 | GEMTRAC1 [1.16] | | CN0t | Unspecified | Unassigned | Permane | |
| 000008L6 | GEMTRAC1 [1.22] | | CN0t | Unspecified | Unassigned | Permane | |
| 000009L6 | GEMTRAC1 [1.30] | | CDN0t | Unspecified | Unassigned | Saturday | |

 If the **volume** count exceeds the maximum set in the **Location Auto Swap Max** field, the display will revert to the original default setting of slot number.

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/location_swap?rev=1522976916

Last update: **2025/01/21 22:07**

