Preferences

The Preferences window, File \rightarrow Preferences, sets basic customization for TapeMaster such as sounds, hidden objects, etc.

| Options | | × |
|---------------------------------|-----------|------|
| Options | | |
| Disable sounds | True | |
| Show hidden Customers | True | |
| Show hidden Media | True | |
| Show hidden Volumes | True | |
| Parent/Child | False | |
| Anonymous Customers | False | |
| Enable Consignment Tab | True | |
| Repository-ID filters | True | |
| Disable Volume List inline edit | False | |
| Location Auto Swap | True | |
| Location Auto Swap Max | 1000 | |
| Show Volume Refresh Clock | True | |
| | | |
| | OK Cancel | Help |

Options

- **Disable sounds**: If set to **True**, all sounds in TapeMaster will be muted.
- Show hidden Customers: If set to True, the Customer Tree will display Customers that have the Hide Customer option in the Customer Properties Window set to True.
- Show hidden Media: If set to True, the Customer Tree will display Media Types that have the Hide Media Type option in the Options Tab of the Media Type Properties Window set to True.
- Show hidden Volumes: If set to True, the Volume List will display Volumes that have the Hide Volume option in the Options Tab of the Volume Properties Window set to True.
- **Parent/Child**: If set to **False**, the Customer Tree will not display Customers with a Parent Customer set in the Customer Properties Window nested under their Parent Customer.
- **Anonymous Customers**: If set to **True**, Customer Descriptions in the Customer Tree will not display.
- Enable Consignment Tab: If set to True, the Consignments tab will appear as an Administration Tab.

- **Repository-ID filters**: If set to **True**, Volumes in the Volume List can be filtered by the Repository-ID instead of the Repository Description.
- **Disable Volume List inline edit**: If set to **True**, inline editing in Volume List will be disabled. (Requires restart)
- Location Auto Swap: If set to True, will display the Volume slot location instead of slot number if inventory quantity is under the Location Auto Swap Max value.
- Location Auto Swap Max sets the maximum number of volumes to enable the Location Auto Swap function. This field only displays when Location Auto Swap is set to true.
- Show Volume Refresh Clock: If set to True a counter will display the time in seconds from the last time the Volume window was refreshed. Changes will take effect on restart of TapeMaster.

From: https://rtfm.tapetrack.com/ - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/preferences

Last update: 2025/01/21 22:07

