

Preferences

The Preferences window, File → Preferences, sets basic customization for TapeMaster such as sounds, hidden objects, etc.



Options

- **Disable sounds:** If set to **True**, all sounds in TapeMaster will be muted.
- **Case Insensitive Filters:** Case is ignored when matching strings against filters.
- **Show hidden Customers:** If set to **True**, the Customer Tree will display Customers that have the **Hide Customer** option in the Customer Properties Window set to **True**.
- **Show hidden Media:** If set to **True**, the Customer Tree will display Media Types that have the **Hide Media Type** option in the Options Tab of the Media Type Properties Window set to **True**.
- **Show hidden Volumes:** If set to **True**, the Volume List will display Volumes that have the **Hide Volume** option in the Options Tab of the Volume Properties Window set to **True**.
- **Parent/Child:** If set to **False**, the Customer Tree will not display Customers with a Parent Customer set in the Customer Properties Window nested under their Parent Customer.
- **Anonymous Customers:** If set to **True**, Customer Descriptions in the Customer Tree will not display.
- **Enable Consignment Tab:** If set to **True**, the Consignments tab will appear as an

Administration Tab.

- **Repository-ID filters:** If set to **True**, Volumes in the Volume List can be filtered by the Repository-ID instead of the Repository Description.
- **Disable Volume List inline edit:** If set to **True**, inline editing in Volume List will be disabled. (Requires restart)
- **Volume List Above Repository List:** Reorganize Volume and Repository windows in the GUI. True = Volumes displayed above Repositories. False = Repositories above Volumes.
- **Location Auto Swap:** If set to **True**, will display the Volume slot location instead of slot number if inventory quantity is under the **Location Auto Swap Max** value.
- **Location Auto Swap Max** sets the maximum number of volumes to enable the Location Auto Swap function. This field only displays when **Location Auto Swap** is set to true.
- **Show Volume Refresh Clock:** If set to **True** a counter will display the time in seconds from the last time the Volume window was refreshed. Changes will take effect on restart of TapeMaster.
- **Show Volume Health Score:** Display the Library Health Score in the Volume Properties window.
- **Volume Description Label:** Custom set the Volume Description Label in the Inventory window.

From:

<https://rtfm.tapetrack.com/> - TapeTrack Documentation

Permanent link:

<https://rtfm.tapetrack.com/master/preferences?rev=1783380956>

Last update: **2026/07/06 23:35**

