

# Slotting

A Slot is a location in a Zone large enough for one Volume.


## Adding Slots to a Repository

To add Slots to a Repository, create a [Zone](#) using the Zone Administration tool in the Administration Menu. Then, follow the steps to Add a Zone to a Repository.

## Manually Add a Volume to a Slot

To manually add a Volume to a Slot, Double-Click a Volume in the Volume List or Right-Click a Volume in the Volume List and select Properties. This will launch the Volume Properties Window.

Select the Target Location tab and enter a Slot number in either the Slot field in the Relative Location window or the Level field and Slot field in the Absolute Location window.

 Click Save and the Volume will be put into a Move to that slot, even if that Volume is moving to a Slot within its Current Repository.

## Automatic Slotting

Automatic Slotting in TapeTrack is done with a Command Line program called TMSS10SlotAllocation that is included in installs of TapeTrack Framework Server and TapeTrack Server Utilities in conjunction with Windows Task Scheduler. TMSS10SlotAllocation must be run on the TapeTrack Server, but it can be launched remotely if necessary.

## Sample Slotting Script

```
TMSS10SlotAllocation -S superuser:-password@tapetrack.domain.com >
"%TMSS10REPORTS%\slotting_report.txt" 2>
"%TMSS10REPORTS%\slotting_error.txt"
```

## Preparing TapeMaster for Automatic Slotting

Before running TMSS10SlotAllocation, Repositories must be set so that Slotting is Enabled. This can be done under the Options Tab of the Repository Properties Window.

Edit Repository: Offsite Vault

Identity Zones Slot Usage Options Usage History Movement History Certification

|  |               |
|--|---------------|
| Allow Deletes                            | False         |
| Allow Overlaps                           | False         |
| De-assign from Container                 | False         |
| Empty Container                          | False         |
| Do not slot if Container                 | False         |
| Do not slot                              | False         |
| Require Tag                              | False         |
| Require Tag Reset                        | False         |
| No re-move                               | False         |
| Disallow backward next move date changes | False         |
| Reset Data Cluster                       | False         |
| Confirm Container Contents               | False         |
| Move Container Contents                  | False         |
| Late Threshold                           | 0             |
| Highwater Offset                         | 0             |
| Movement Mode                            | None          |
| Next Repository                          | Library       |
| Enable Slotting                          | True          |
| Slot Assignment Options                  |               |
| Slotting Mode                            | IntelliSlot   |
| Ignore Home Slot                         | False         |
| Do not reslot                            | False         |
| Retain moving slot                       | False         |
| Slotting Order                           | Movement Time |
| Capacity                                 |               |
| Coordinates                              |               |

Save Cancel Help

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: <https://rtfm.tapetrack.com/master/slotting?rev=1505323690>

Last update: **2025/01/21 22:07**

