


TapeMaster Configuration File

To modify TapeMaster, open TMSSMaster.cfg in a plain text editor such as Notepad. TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

Remove Slot Level Display

Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

    /*
    variables = {
        TMSLEVELNAMES = "A,B,C";
    };
    */

    showparent = true;
};

defaults = {
```

Remove comment tags /* & */ from above and below variables.

Change the line of code
TMSLEVELNAMES = "A,B,C";
to
TMSNOLEVELSLOT = "true";


```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
  //
  // When exporting data to email send to the following addresses
  //
  email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

  variables = {
    TMSSNOLEVELSLOT = "true";
  };

  showparent = true;
};

defaults = {
```


and save file

 Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file or other file extension.

To check the modification was successful:


Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below.

Before modification - TapeMaster displaying Zone, shelf and slot.



| ID | Current Location | Target Location | Flags | Move Time | Due in | Container | Next Move |
|----------|------------------|-----------------|-------|-----------|-------------|------------|-----------|
| 000001L5 | Rack_01 [6.1] | | CNO | | Unspecified | Unassigned | Permanent |
| 000002L5 | Rack_01 [10.10] | | CGNO | | Unspecified | Unassigned | Permanent |
| 000003L5 | Rack_03 [10.10] | | CNO | | Unspecified | Unassigned | Permanent |
| 000004L5 | Library | | CnN | | Unspecified | Unassigned | Permanent |
| 000005L5 | Library | | CnN | | Unspecified | Unassigned | Permanent |
| 000006L5 | Library | | CEnN | | Unspecified | Unassigned | Permanent |

After modification - TapeMaster displaying Zone and shelf only.



| ID | Current Location | Target Location | Flags | Move Time | Due in | Container | Next Move |
|----------|------------------|-----------------|-------|-----------|-------------|------------|-----------|
| 000001L5 | Rack_01 [6] | | CNO | | Unspecified | Unassigned | Permanent |
| 000002L5 | Rack_01 [10] | | CGNO | | Unspecified | Unassigned | Permanent |
| 000003L5 | Rack_03 [10] | | CNO | | Unspecified | Unassigned | Permanent |
| 000004L5 | Library | | CnN | | Unspecified | Unassigned | Permanent |
| 000005L5 | Library | | CnN | | Unspecified | Unassigned | Permanent |
| 000006L5 | Library | | CEnN | | Unspecified | Unassigned | Permanent |

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://rtfm.tapetrack.com/technote/config_file_tapemaster?rev=1530235049

Last update: **2025/01/21 22:07**

