


TapeMaster Configuration File

To modify TapeMaster, open TMSSMaster.cfg in a plain text editor such as Notepad. TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

The config file has comments throughout the code to either disable the execution of unused code blocks or add explanation to the available functions. *Block quotes look like /* */, anything between these characters are treated as comments and not code. Anything after the characters // are treated as comments and not code for that line.* **==== Remove Slot Level Display ==== Locate the section variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
  //
  // When exporting data to email send to the following addresses
  //
  email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

  /*
  variables = {
    TMSSEVELNAMES = "A,B,C";
  };
  */

  showparent = true;
};

defaults = {
```



Remove comment tags / & */ from above and below variables. Change the line of code*

TMSSEVELNAMES = "A,B,C";

to

TMSSENOLEVELSLOT = "true";

```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
  //
  // When exporting data to email send to the following addresses
  //
  email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

  variables = {
    TMSSNOLEVELSLOT = "true";
  };

  showparent = true;
};

defaults = {
```

and save file. <note important>Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file or other file extension.</note> To check the modification was successful: Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below. Before modification - TapeMaster displaying Zone, shelf and slot.



ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
000001L5	Rack_01 [6.1]		CNO		Unspecified	Unassigned	Permanent
000002L5	Rack_01 [10.10]		CGNO		Unspecified	Unassigned	Permanent
000003L5	Rack_03 [10.10]		CNO		Unspecified	Unassigned	Permanent
000004L5	Library		CnN		Unspecified	Unassigned	Permanent
000005L5	Library		CnN		Unspecified	Unassigned	Permanent
000006L5	Library		CEnN		Unspecified	Unassigned	Permanent

After modification - TapeMaster displaying Zone and shelf only.

ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move
000001L5	Rack_01 [6]		CNO		Unspecified	Unassigned	Perman
000002L5	Rack_01 [10]		CGNO		Unspecified	Unassigned	Perman
000003L5	Rack_03 [10]		CNO		Unspecified	Unassigned	Perman
000004L5	Library		CnN		Unspecified	Unassigned	Perman
000005L5	Library		CnN		Unspecified	Unassigned	Perman
000006L5	Library		CEnN		Unspecified	Unassigned	Perman

<note important>If when opening TapeTrack TapeMaster you receive an error - **Failed to read configuration file (TMSSMaster.cfg): Line() - Syntax error** check the configuration file that you have used plain ASCII quotes (" ") and not rich text quotes (" ") and that the replaced text is correct.</note>

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

https://rtfm.tapetrack.com/technote/config_file_tapemaster?rev=1541633764

Last update: **2025/01/21 22:07**

