

TapeMaster Configuration File

To modify TapeMaster, open TMSSMaster.cfg in a plain text editor such as Notepad. TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack TapeMaster).

The config file has comments throughout the code to either disable the execution of unused code blocks or add explanation to the available functions. *Block quotes look like /* */, anything between these characters are treated as comments and not code. Anything after the characters // are treated as comments and not code for that line.* </note> ===== Remove Slot Level Display ===== Locate the section **variables**



```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

    /*
    variables = {
        TMSSLEVELNAMES = "A,B,C";
    };
    */
    showparent = true;
};

defaults = {
```

Remove comment tags /* & */ from above and below variables. Change the line of code

TMSSLEVELNAMES = "A,B,C";
to
TMSSNOLEVELSLOT = "true";

```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "mailto1@tapetrack.com", "mailto2@tapetrack.com" ];

    variables = {
        TMSSNOLEVELSLOT = "true";
    };

    showparent = true;
};

defaults = {
```

and save file. *<note important>Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file or other file extension.</note>* To check the modification was successful: Login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below. Before modification - TapeMaster displaying Zone, shelf and slot.



Volumes								
ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move	
000001I5	Rack_01 [6.1]		CNO	Unspecified	Unassigned	Permanent		
000002I5	Rack_01 [10.10]		CGNO	Unspecified	Unassigned	Permanent		
000003I5	Rack_03 [10.10]		CNO	Unspecified	Unassigned	Permanent		
000004I5	Library		CnN	Unspecified	Unassigned	Permanent		
000005I5	Library		CnN	Unspecified	Unassigned	Permanent		
000006I5	Library		CEnN	Unspecified	Unassigned	Permanent		

After modification - TapeMaster displaying Zone and shelf only.

Volumes								
ID	Current Location	Target Location	Flags	Move Time	Due in	Container	Next Move	
000001I5	Rack_01 [6]		CNO	Unspecified	Unassigned	Permanent		
000002I5	Rack_01 [10]		CGNO	Unspecified	Unassigned	Permanent		
000003I5	Rack_03 [10]		CNO	Unspecified	Unassigned	Permanent		
000004I5	Library		CnN	Unspecified	Unassigned	Permanent		
000005I5	Library		CnN	Unspecified	Unassigned	Permanent		
000006I5	Library		CEnN	Unspecified	Unassigned	Permanent		

<note important>If when opening TapeTrack TapeMaster you receive an error - Failed to read configuration file (TMSSMaster.cfg): Line() - Syntax error check the configuration file that you have used plain ASCII quotes (" ") and not rich text quotes (" ") and that the replaced text is correct.</note>

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**



Permanent link:
https://rtfm.tapetrack.com/technote/config_file_tapemaster?rev=1541633764

Last update: **2025/01/21 22:07**