

Upgrading Framework Server

As upgrading the Framework Server requires alterations around the database, following best practice, backing up the entire server install directory, including the executables and var directory using a utility such as WinZip is highly recommended before starting the upgrade process.

The Framework Server executable also contains installation files for both TapeMaster and Server Utilities. These installations will be automatically executed after the completion of the Framework Server installation.

If you are installing the Framework Server on a remote server and want to install TapeMaster and/or the Server Utilities on another computer, simply cancel the installation process of these software packages.

TapeMaster and the Server Utilities installation files (along with TapeTrack Lite and Checkpoint) can be downloaded on their own for installation on separate computers from <http://mirror-us.tapetrack.com/>

Download Installer

- [Framework Server 64 Bit](#)
- [Framework Server 32 Bit](#)
- [Linux](#)

Backup Before Starting Upgrade

- Notify your users in advance of the upgrade.
- [Stop the TapeTrack Service](#).
- Take a [backup](#) of the entire server install directory, including the executables and var directory using a utility such as WinZip.
- Rename the `\TapeTrack\TapeTrack Framework Server\var` directory to `\TapeTrack\TapeTrack Framework Server\var.old`.

Remove Current Installation

The following instructions are the suggested method for Windows 10.

If you are running another operating system, please follow the instructions for that system.

- Open the Start menu.
- Click Settings (Gear icon).
- Click System on the Settings menu.
- Select Apps & features from the left pane to display a list of all installed apps.
- Select TapeTrack Framework Server from the list by left clicking.
- Click the Uninstall button that appears.

- Click the Uninstall pop-up button to confirm.


If you are upgrading TapeMaster and/or Server Utilites on the same computer as the Framework Server uninstall these software packages using the instructions above now.

Install New Release


Locate the executable you downloaded, setup.exe, and double click to initiate the installation.




Click Next > to start the Install Shield Wizard.




After reading and agreeing to the License Agreement click I accept the terms in the license agreement and Next > to proceed




Confirm the installation directory is correct, or click Change to select another installation directory. Click Next > to proceed.



Click Install to begin the installation



Click Finish to exit the installer.




TapeMaster and Server Utilites

If you are installing TapeMaster and/or Server Utilites on this computer, click Next on the InstallSheild window and follow the instructions (bypassing the uninstall process) at:


- [TapeMaster](#)

- [Server Utilities](#)


If you are not installing TapeMaster and/or Server Utilities on this computer, click Cancel on the InstallShield window.



Click Yes on the popup confirmation.



Click Finish to exit the installer.



See Also

- [Upgrading TapeMaster](#)
- [Upgrading Lite](#)
- [Upgrading Server Utilities](#)
- [Upgrading Checkpoint](#)

From: <https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/technote/upgrade_server?rev=1574732759

Last update: **2025/01/21 22:07**

