

Pick (Scanning out)

The Pick Option in the Toolbar will set the Start Scan operation to Pick Mode.

[image](#)

There are three options that Pick Mode can operate in:

- Default: When the Pick in Volser Order option is not selected, the Speech Subsystem will announce the Volumes to be picked in the order of their Slot Number.
- Pick in Volser Order: When the Pick in Volser Order option is selected, the Speech Subsystem will announce the Volumes to be picked in the order of their Volume-ID.
- Pick out of sequence: When the Pick out of sequence option is selected, Volumes can be scanned in any order without receiving an Error in the Errors Tab. The Speech Subsystem will still announce Volumes in the order set by the Pick in Volser Order Tick box.

During Pick Mode, the Speech Subsystem will announce either:

- Mode 0 : Volume only.
- Mode 1 : Zone and Volume.
- Mode 2 : Zone, Slot and Volume

Set the mode required by entering the mode control character (0, 1 or 2).

Volumes, Slots and Zones, so that the Volumes can be moved from the Sending Repository to the Receiving Repository.

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
<https://rtfm.tapetrack.com/checkpoint/pick?rev=1513037577>

Last update: **2025/01/21 22:07**

