

TMSS10LibraryHealth

Synopsis

TMSS10LibraryHealth [-S logon string] [-V volume filter] [-i ignore no library health option]

Description

TMSS10Libraryhealth produces a report on each [Customers Media Health](#) status.

Options

- -S The logon string argument sets the [Server logon information](#)
- -V [Volume Filter](#) which can be used to filter the traversal of [Customer](#), [Media](#), [Volume](#), [Repository](#) and [Flag](#) values.
- -i Ignore the **no library health** option.

Notes

The **No Library Health** can be set on the [Media Properties Options Tab](#).

Technical Support

The TapeTrack Software is commercially supported by a full time help desk staff. If you are experiencing problems or want some advice on how to configure or use the product please see the [Accessing Technical Support](#) page.

Exit Statuses

1. **zero** Program has ended successfully.
2. **non-zero** Program has not ended successfully.

Environment

[TMSSSERVERPROXY](#) If defined the program will route all TapeTrack TCP/IP traffic through a HTTPS proxy. The value of the variable should be in the format user:password@host:port. To debug the proxy connection use variable TMSSAPILOGDIR.

TMSSAPILOGDIR If defined the program will write out a trace file to this directory.

TMSSPPATH When no password value is passed in the logon string the program will look for the password in file C:/tapetrack/pw/batch, where user is the user value passed in the logonstring. If you wish to change this default path, you can set the path in TMSSPPATH.

TMSSNOMD5 If defined the program will not MD5 hash passwords before sending them to the TapeTrack Server. This is required when relying on Windows Active Directory authentication. It should be noted that although the password is not being hashed, it is still encrypted during transmission.

Files

- stdout:** Output Reports.
- stderr:** Diagnostic messages.
- stdin:** Program input.

Example

Command Line Syntax

```
tmss10libraryhealth -S user:-password@server -V "US02.*.*"
```

Output

System: TapeTrack				
Report Description: Library Health Report				
Report Notes: Customer(Los Angeles Data Center)				
Report Width: 63 bytes				
Media		Health Status		
-----		-----		
LT0 Cartridge		Not ideal		
		Reason		Penalty
		-----		-----
		No Sync		-30
		No DR Strategies for 4 days		-10
		No Offsite activity for 4 days		-10
		Volume-ID	Current	Target
		Last-Scanned Overdue		
Audit Warning	Audit Date			

Changelog

Cannot load rss feed.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/cli/tmss10libraryhealth?rev=1578360234>

Last update: **2025/01/21 22:07**

