2025/12/01 14:52 1/3 TMSS10LibraryHealth

TMSS10LibraryHealth

TMSS10Libraryhealth produces a report on each Customers Media Health status.

Synopsis

TMSS10LibraryHealth [-S logon string] [-V volume filter] [-i ignore no library health option]

Options

- -S The logon string argument sets the Server logon information
- V Volume Filter which can be used to filter the traversal of Customer, Media, Volume, Repository and Flag values.
- -i Ignore the **no library health** option.

Notes

The No Library Health can be set on the Media Properties Options Tab.

Technical Support

The TapeTrack Software is commercially supported by a full time help desk staff.

If you are experiencing problems or want some advice on how to configure or use the product please see the Accessing Technical Support page.

Exit Statuses

- 1. **zero** Program has ended successfully.
- 2. **non-zero** Program has not ended successfully.

Environment

TMSSSERVERPROXY If defined the program will route all TapeTrack TCP/IP traffic through a HTTPS proxy. The value of the variable should be in the format user:password@host:port. To debug the proxy connection use variable TMSSAPILOGDIR.

TMSSAPILOGDIR If defined the program will write out a trace file to this directory.

TMSSPWPATH When no password value is passed in the logon string the program will look for the

Last update: 2025/01/21 22:07

password in file C:/tapetrack/pw/batch, where user is the user value passed in the logonstring. If you wish to change this default path, you can set the path in TMSSPWPATH.

TMSSNOMD5 If defined the program will not MD5 hash passwords before sending them to the TapeTrack Server. This is required when relying on Windows Active Directory authentication. It should be noted that although the password is not being hashed, it is still encrypted during transmission.

Files

stdout: Output Reports. **stderr:** Diagnostic messages.

stdin: Program input.

Example

Command Line Syntax

```
tmss10libraryhealth -S user:-password@server -V "US02.*.*"
```

Output

```
System: TapeTrack
Report Description: Library Health Report
      Report Notes: Customer(Los Angeles Data Center)
      Report Width: 63 bytes
Media
                   Health Status
LTO Cartridge
                   Not ideal
                   Reason
                                                Penalty
                   -----
                   No Sync
                                                   - 30
                   No DR Strategies for 4 days
                                                    - 10
                   No Offsite activity for 4 days -10
                   Volume-ID Current Target Last-Scanned Overdue
Audit Warning Audit Date
```

https://rtfm.tapetrack.com/ Printed on 2025/12/01 14:52

2025/12/01 14:52 3/3 TMSS10LibraryHealth

Changelog

Cannot load rss feed.

From:

https://rtfm.tapetrack.com/ - TapeTrack Documentation

Permanent link:

https://rtfm.tapetrack.com/cli/tmss10libraryhealth?rev=1578366756

Last update: 2025/01/21 22:07

