## **Technical Note: Configuration File**

Modifying config file in TapeMaster and Lite to remove slot display.

Open TMSSMaster.cfg in a plain text editor such as Notepad. TMSSMaster.cfg can be found in the TapeTrack/TapeMaster install directory (default C:\Program Files\TapeTrack\TapeTrack\TapeTrack\TapeMaster).

## Locate the section variables

```
TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com" ];

/*
    variables = {
        TMSSLEVELNAMES = "A,B,C";
    };
    */
    showparent = true;
};
defaults = {
```

Remove comment tags /\* & \*/ from above and below variables.

Change TMSSLEVELNAMES = "A,B,C"; to TMSSNOLEVELSLOT = "true";

```
Image: TMSSMaster.cfg - Notepad
File Edit Format View Help
options = {
    //
    // When exporting data to email send to the following addresses
    //
    email = [ "emailto1@tapetrack.com", "emailto2@tapetrack.com"];

variables = {
    TMSSNOLEVELSLOT = "true";
    };

showparent = true;
};

defaults = {
```


and save file



Make sure that you have sufficient rights to save file to directory and to save as TMSS10Master.cfg and not as a text file.


To check the modification was successful, login to TapeMaster and open slotted media to check display of volume location is now restricted to Zone and shelf as illustrated by the images below..

Before modification - displaying Zone, shelf and slot.



After modification - displaying Zone and shelf only.

https://rtfm.tapetrack.com/ Printed on 2025/12/01 11:16



Open TMSSLite.cfg in Notepad

image.png

Remove comment tags /\* & \*/ from above and below variables.

Change TMSSLEVELNAMES = "A,B,C"; to TMSSNOLEVELSLOT = "true";

And save file

image.png

From:

https://rtfm.tapetrack.com/ - TapeTrack Documentation

Permanent link:

https://rtfm.tapetrack.com/technote/config\_file?rev=1528944844

Last update: 2025/01/21 22:07

