Restoring Database From DB_Hotbackup Snapshot

Restoring database to a new installation.

Install the TapeTrack Framework Server software on your computer

Stop the service

S	TapeTrack Server He	lper						
	Service							
	Name		TMSS10SVC					
	Status		Running					
	Process ID	N	20584					
	Binary		C:\Program Files\TapeTr	ack\TapeTrack	Framework Server\TMSS10Ser	ver.exe		
	Options							
	Home Directory							
	Port		5000					
	Syslogd Server							
	Enable Replication		True					
	Log File Name Type		0					
la la	Save Se	ervice Setting	JS					
Control Service				Update Soft	vare	Edit/View Files		
1	Stop		Start		Download and Update	DB CONFIG		
	0							

Navigate to the backup snaphot directory and copy all files to your clipboard.

Navigate to the TapeTrack database folder (default install location C:\Program Files\TapeTrack\TapeTrack Framework Server\var\db)

Right click in the db folder and select paste to copy the files in, select **Replace files** option to overwrite the files in the database. It is important that you paste the files in over the current files and not just delete the original files as not all required files to run the server are contained in the backup snapshot. This method maintains the integrity of the db files required for restore and restart of the server.

Right click the log file log.000000001 and select cut. Navigate to the folder var/dblogs, delete the current log file and paste in the one from your clipboard.

Start the service and open TapeMaster to check the database restore is correct.

S TapeTrack Server Helper							
	Service						
	Name	TMSS10SVC					
	Status	Start Pending					
	Process ID	4472					
	Binary	C:\Program Files\TapeTrack\TapeTrack Framework Server\TMSS10Server.exe					
	Options						
	Home Directory						
	Port	5000					
	Syslogd Server						
	Enable Replication	True					
	Log File Name Type	0					
Save Service Settings							
Control Service Dpdate Software Edit/View Files							
	Stop	Start Download and Update DB_CONFIG					

If you have restored the database onto another computer system you will need to apply for a new license key as the new MAC address will make the old key invalid.

