

# TMSS10MoveLocation

TMSS10MoveLocation puts selected [Volumes](#) in a move from one [Repository](#) to another.

## Synopsis

```
TMSS10MoveLocation [-C move only if container moving] [-S logon string] [-V volume] [-X skip volumes assigned to a container] [-c configuration file] [-e exclude volumes already moving] [-f from repository] [-l apply move lock during move] [-t to repository]
```

## Options

- -C Move [Volume](#) only when assigned Container is moving and matches move requirements.
- -S The Logon string argument sets the [Server Logon Information](#).
- -V [Volume Filter](#) which can be used to filter the traversal of [Customer](#), [Media](#), [Volume](#), [Repository](#) and [Flag](#) values.
- -X Skip any volumes already assigned to a container.
- -c The config file argument specifies the path to the Batch Configuration File. The Batch Configuration File allows you to perform advanced traversal of [Customer](#), [Media](#) and [Volumes](#), perform advanced Barcode pre and post processing and route program output to syslogd.
- -e Exclude any [Volumes](#) that are already in a Move Status.
- -f [Repository](#) to Move [Volumes](#) from.
- -l Apply a move-lock to [Volumes](#) during move.
- -t [Repository](#) to move [Volumes](#) to.

If an argument value starts with the value FI:, the value for that attribute will be read from the file name specified immediately after it. For example, if a file named ACME\_volumes has the content ACME\_\*.\*, specifying FI:/etc/ACME\_volumes will have the same effect as -V ACME.\*.\*. Using FI: to refer to a file for an attribute value works for all attributes.

If the pattern being matched starts with \*LIST: then rather than matching the literal value, each record in the file specified as \*LIST:filename will be tested. If one matches the match will succeed.

2021/06/16 02:14 · Scott Cunliffe

[include page](#)

## Technical Support

The TapeTrack Software is commercially supported by a full time help desk staff.

If you are experiencing problems or want some advice on how to configure or use the product please see the [Accessing Technical Support](#) page.

Exit Statuses

1. **zero** Program has ended successfully.
2. **non-zero** Program has not ended successfully.

Environment

Files

**stdout:** Output Reports.  
**stderr:** Diagnostic messages.  
**stdin:** Program input.

Example

Command line syntax

Move all US02 LTO Volumes with a Barcode ending in 5L6.

```
TMSS10MoveLocation -S user:-password@server -V "US02.LT0.*5L6" -f "LIBR" -t "OFFS"
```

Output

|   |                   |         |               |
|---|-------------------|---------|---------------|
| System: TapeTrack   |                   |         |               |
| Report Description: Volumes Moved   |                   |         |               |
| Report Notes: From(LIBR) To(OFFS)   |                   |         |               |
| Production Time: Monday, November 27, 2017 - 12:56:38 (AUS Eastern Daylight Time) |                   |         |               |
| Report Width: 92 bytes  |                   |         |               |
| Seq.  | Barcode           | From    | To            |
| Container   |                   |         |               |
| -----   |                   |         |               |
|   |                   |         |               |
| 1   | US02.LT0.000015L6 | Library | Offsite Vault |
| 2   | US02.LT0.000035L6 | Library | Offsite Vault |
| 3   | US02.LT0.000065L6 | Library | Offsite Vault |
| 4   | US02.LT0.000075L6 | Library | Offsite Vault |
| 5   | US02.LT0.000085L6 | Library | Offsite Vault |
| 6   | US02.LT0.000095L6 | Library | Offsite Vault |

|       |                   |         |               |
|-------|-------------------|---------|---------------|
| 7     | US02.LT0.000105L6 | Library | Offsite Vault |
| 8     | US02.LT0.000115L6 | Library | Offsite Vault |
| 9     | US02.LT0.000125L6 | Library | Offsite Vault |
| 10    | US02.LT0.000135L6 | Library | Offsite Vault |
| 11    | US02.LT0.000145L6 | Library | Offsite Vault |
| 12    | US02.LT0.000155L6 | Library | Offsite Vault |
| 13    | US02.LT0.000165L6 | Library | Offsite Vault |
| 14    | US02.LT0.000175L6 | Library | Offsite Vault |
| 15    | US02.LT0.000185L6 | Library | Offsite Vault |
| 16    | US02.LT0.000195L6 | Library | Offsite Vault |
| 17    | US02.LT0.000205L6 | Library | Offsite Vault |
| 18    | US02.LT0.000215L6 | Library | Offsite Vault |
| 19    | US02.LT0.000225L6 | Library | Offsite Vault |
| 20    | US02.LT0.000235L6 | Library | Offsite Vault |
| 21    | US02.LT0.000245L6 | Library | Offsite Vault |
| 22    | US02.LT0.000255L6 | Library | Offsite Vault |
| 23    | US02.LT0.000265L6 | Library | Offsite Vault |
| 24    | US02.LT0.000275L6 | Library | Offsite Vault |
| 25    | US02.LT0.000285L6 | Library | Offsite Vault |
| 26    | US02.LT0.000295L6 | Library | Offsite Vault |
| 27    | US02.LT0.000305L6 | Library | Offsite Vault |
| 28    | US02.LT0.000315L6 | Library | Offsite Vault |
| ----- |                   |         |               |
| ----- |                   |         |               |

## Changelog

Cannot load rss feed.

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/cli/tmss10moveLocation?rev=1623812222>

Last update:

**2025/01/21 22:07**

