

setvar2date

SetVar2Date

Set a local variable to a date value.

Phase

This instruction is used by the TapeTrack INI Engine.

Syntax

SetVar2Date(varname, date, value);

string varname;

string date;

string value;

varname	The name of the local variable that is to be set.
date	The string representing the date required in one of the following formats:
*[+ -]n	Today's date plus or minus an optional number of days.
*	Today.
*-100	100days ago.
*+30	30 days into the future.
YYYY-MM-DD	The date in ISO date format.
2010-12-31	The 31st of December 2010.
Y y[+ -]n[+ -]m[+ -]d	The beginning or end of the year, + or - a number of years, + or - a number of months, + or - a number of days.
Y-0	The start of the current year.
y-0	The end of the current year.
Y-1	The start of last year.
Y-1+3+3	The 3rd day of the third month of last year.
Y+10+3+3	The 3rd day of the 3rd month of the year 10 years from now.
M m[+ -]m[+ -]d	The beginning or end of the month, + or - a number of months, + or - a number of days.
M-0	The start of the current month.
m-0	The end of the of the current month.
M-1	The start of last month.
M-1+3	The 3rd day of last month.
value	The date value in strftime(3) format.

Example

SetVar2Date: Set variable YESTERDAY to yesterday's date.

SetVar2Date(YESTERDAY, "*-1", "Y-m-d"); WriteMsg("Yesterday was %YESTERDAY"); ===== Example ===== **SetVar2Date: Set variable START to the first day of this year and END to the last.** SetVar2Date(START, "Y-0", "Y-m-d");
SetVar2Date(END, "y-0", "Y-m-%d");
WriteMsg("Date range is END");

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/engine/import/setvar2date?rev=1534282006>Last update: **2025/01/21 22:07**