

setvar2date

## SetVar2Date

Set a local variable to a date value.

### Phase

This instruction is used by the TapeTrack INI Engine.

### Syntax

**SetVar2Date**(varname, date, value);

*string varname;*

*string date;*

*string value;*

varname	The name of the local variable that is to be set.
date	The string representing the date required in one of the following formats:
*[+ -]n	Today's date plus or minus an optional number of days.
*	Today.
*-100	100days ago.
*+30	30 days into the future.
YYYY-MM-DD	The date in ISO date format.
2010-12-31	The 31st of December 2010.
Y y[+ -]n[+ -]m[+ -]d	The beginning or end of the year, + or - a number of years, + or - a number of months, + or - a number of days.
Y-0	The start of the current year.
y-0	The end of the current year.
Y-1	The start of last year.
Y-1+3+3	The 3rd day of the third month of last year.
Y+10+3+3	The 3rd day of the 3rd month of the year 10 years from now.
M m[+ -]m[+ -]d	The beginning or end of the month, + or - a number of months, + or - a number of days.
M-0	The start of the current month.
m-0	The end of the of the current month.
M-1	The start of last month.
M-1+3	The 3rd day of last month.
value	The date value in strftime(3) format.

### Example

**SetVar2Date: Set variable YESTERDAY to yesterday's date.**

SetVar2Date(YESTERDAY, "*-1", "%%Y-%%m-%%d");
WriteMsg("Yesterday was %YESTERDAY");

## Example

**SetVar2Date: Set variable START to the first day of this year and END to the last.**

SetVar2Date(START, "Y-0", "%%Y-%%m-%%d");;
SetVar2Date(END, "y-0", "%%Y-%%m-%%d");;
WriteMsg("Date range is \$START through \$END");

From:

<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:

<https://rtfm.tapetrack.com/engine/import/setvar2date?rev=1534282220>

Last update: **2025/01/21 22:07**

