Slotting

A Slot is a location in a Zone large enough for one Volume. Slotting is a process of allocating a volume to a particular slot to allow documentation of the exact storage location of that volume.

Adding Slots to a Repository

To add Slots to a Repository, create a Zone using the Zone Administration tool in the Administration Menu. Then, follow the steps to Add a Zone to a Repository.

Manually Add a Volume to a Slot

To manually add a Volume to a Slot, Double-Click a Volume in the Volume List or Right-Click a Volume in the Volume List and select Properties. This will launch the Volume Properties Window.

Select the **Target Location** tab and enter a Slot number in either the Slot field in the Relative Location window or the Level field and Slot field in the Absolute Location window.

t Volume: 000022	L5				:
Datasets	1 Techbores	VeriScore [™]	Q DR Strategies	Options	Catalog
ldentity 🚟	Target Location	Current Location	Scanned Locat	tion 🛛 🖊 Notes	16 History
-Relative Location					
Repository-ID	OFFS 0	ffsite Vault	~		
Slot	5 ≑	Maximum=60		_	
Absolute Location]				
Zone-ID	Drawer 1 divider 1		\sim		
Level	1 ≑				
Slot	<mark>5</mark> ≑				
	istics				
- opadio otali					

Click Save and the Volume will be put into a Move to that slot, even if that Volume is moving to a Slot within its Current Repository.

Click F5 in the inventory window to update the display to show new target slotting.

Automatic Slotting

Automatic Slotting in TapeTrack is done with a Command Line program called TMSS10SlotAllocation that is included in installs of TapeTrack Framework Server and TapeTrack Server Utilities in

conjunction with Windows Task Scheduler.

TMSS10SlotAllocation must be run on the TapeTrack Server, but it can be launched remotely if necessary.

Sample Slotting Script

```
TMSS10SlotAllocation -S superuser:-password@tapetrack.domain.com >
"%TMSS10REPORTS%\slotting_report.txt" 2>
"%TMSS10REPORTS%\slotting_error.txt"
```

Preparing TapeMaster for Automatic Slotting

Before running TMSS10SlotAllocation, Repositories must be set so that Slotting is Enabled. This can be done under the Options Tab of the Repository Properties Window.

🖗 Identity 💿 Zones 🖳 Slot Usage	🗃 Options 🔟 Usage History 🔟 Movement History 🗔 Certificat	ion		
Allow Deletes	False	^		
Allow Overlaps	False			
De-assign from Container	False			
Empty Container	False			
Do not slot if Container	False			
Do not slot	False			
Require Tag	False			
Require Tag Reset	False			
No re-move	False			
Disallow backward next move date changes	False			
Reset Data Cluster	False			
Confirm Container Contents	False			
Move Container Contents	False			
Late Threshold	0			
Highwater Offset	0			
Movement Mode	None			
Next Repository	Library			
Enable Slotting	True			
Slot Assignment Options				
Slotting Mode	IntelliSlot			
Ignore Home Slot	False			
Do not reslot	False			
Retain moving slot	False			
Slotting Order	Movement Time			
Capacity				
Coordinates				
		~		
	Save Cancel Help	5		

Slotting Mode: There are three Slotting Modes:

- IntelliSlot: The Slotting batch process will Slot Volumes in groups by Consignment or Slotting Order (see below) until the Highwater Offset (see above) is reached. At this point, empty Slots will be filled on a First Available Status.
- First Available: Volumes will be put in the first available Slot in their Repository and will not be grouped.
- Bypass: When Volumes are automatically confirmed (see above), they will not be assigned Slots.
- Ignore Home Slot: If a Volume has been assigned a Home Slot in the Options Tab of the Volume Properties Window, this Repository will ignore it and Slot using the above parameters.
- Slotting Order: There are three orders with which Volumes may be assigned Slots: •Movement Time: Volumes will be assigned Slots based on when they arrived at the selected Repository.
- From Location: Volumes will be assigned Slots based on which Repository they were sent from.
- Volume-ID: Volumes will be assigned Slots in the alphanumeric order based on their Volume-

IDs.

From: https://rtfm.tapetrack.com/ - **TapeTrack Documentation**

Permanent link: https://rtfm.tapetrack.com/master/slotting?rev=1508291666



Last update: 2025/01/21 22:07