

Data Extraction From Source

Data is extracted from your backup software and saved into a Sync source file. The Sync source file is then read into the synchronization process using a definition file to translate the information to TapeTrack formatting.

Extracting Information

The source file information extract will vary depending on your backup software.

Data Extraction From Networker

Using the administrative tool `mminfo`, the Volume data needs to be extracted from the Networker save sets and exported into CSV file format.

To get a report that is suitable for the TapeTrack Sync command, the following minimum arguments should be used:

```
mminfo -xc, -a -r "volume,barcode,family,type,location,pool" > report.csv
```

Data Extraction From TSM

Using the Tivoli Storage Manager administrative tool `dsmadm`, the Volume data needs to be extracted from both the DRM and Volume tables and exported into csv file format.

To get a report that is suitable for the TapeTrack Sync command, the following minimum arguments should be used:

From the DRM table:

From the DRM table, select the fields:

- `volume_name`: Used to determine the [Volume-ID](#) in TapeTrack.
- `state`: Used to determine the location the [Volume](#) should be.
- `stgpool_name`: Used to set the [Volume Description](#).

```
dsmadm -dataonly=yes -id=userid -pa=password -  
tcpserveraddress=tsm01.gazillabyte.local \  
-displaymode=table -outfile=TSM-DRM.csv -commadelimited "select  
volume_name,state,stgpool_name from drmedia"
```

From the Volume table:

From the [Volume](#) table, select the fields:

- volume_name: Used to determine the [Volume-ID](#) in TapeTrack
- location: Used to determine the location the [Volume](#) is.
- stgpool_name: Used to set the [Volume Description](#).

```
dsmadm -dataonly=yes -id=userid -pa=password -  
tcpserveraddress=tsm01.gazillabyte.local \  
-displaymode=table -outfile=TSM-VOL.csv -commadelimited "select  
volume_name,location,stgpool_name from volumes"
```

Data Extraction For VEEAM

VEEAM differs from other backup software in that a direct ODBC connection is made using the definition file rather than extracting the data to file and then using a definition file to read it.

Sample code placed at the beginning of the definition to connect to sample database veeam2.

```
# Connect to Veeam database  
SetODBC("DSN=veeam2");  
# Extract data  
SetSQL("SELECT [barcode],[media_pool_id],[last_write_time] FROM  
[VeeamBackup].[dbo].[Tape.tape_mediums]");
```

From:
<https://rtfm.tapetrack.com/> - **TapeTrack Documentation**

Permanent link:
https://rtfm.tapetrack.com/sync/data_extraction?rev=1622605359

Last update: **2025/01/21 22:07**

